

Spectrum Analyzer

GSP-9300

PROGRAMMING MANUAL

GW INSTEK PART NO. 82SP-930A0E01



ISO-9001 CERTIFIED MANUFACTURER

GW INSTEK

This manual contains proprietary information, which is protected by copyright. All rights are reserved. No part of this manual may be photocopied, reproduced or translated to another language without prior written consent of Good Will company.

The information in this manual was correct at the time of printing. However, Good Will continues to improve products and reserves the rights to change specification, equipment, and maintenance procedures at any time without notice.

Table of Contents

SAFETY INSTRUCTIONS 2

GETTING STARTED 7

 GSP-9300 Introduction 8

 Accessories 11

 Appearance 12

REMOTE CONTROL 25

 Interface Configuration 26

 Command Syntax 49

 Status Registers 54

 Command List 64

APPENDIX227

 Binary Coded Decimal Table 227

S SAFETY INSTRUCTIONS

This chapter contains important safety instructions that you must follow during operation and storage. Read the following before any operation to ensure your safety and to keep the instrument in the best possible condition.

Safety Symbols

These safety symbols may appear in this manual or on the instrument.



WARNING

Warning: Identifies conditions or practices that could result in injury or loss of life.



CAUTION

Caution: Identifies conditions or practices that could result in damage to the instrument or to other properties.



DANGER High Voltage



Attention Refer to the Manual



Earth (ground) Terminal



Frame or Chassis Terminal



Do not dispose electronic equipment as unsorted municipal waste. Please use a separate collection facility or contact the supplier from which this instrument was purchased.

Safety Guidelines

General Guideline



CAUTION

- Do not place any heavy object on the instrument.
- Avoid severe impact or rough handling that leads to damaging the instrument.
- Do not discharge static electricity to the instrument.
- Use only mating connectors, not bare wires, for the terminals.
- Ensure signals to the RF input do not exceed +30dBm.
- Ensure reverse power to the TG output terminal does not exceed +30dBm.
- Do not supply any input signals to the TG output.
- Do not block the cooling fan opening.
- Do not disassemble the instrument unless you are qualified.

(Measurement categories) EN 61010-1:2010 specifies the measurement categories and their requirements as follows. The instrument falls under category II.

- Measurement category IV is for measurement performed at the source of low-voltage installation.
- Measurement category III is for measurement performed in the building installation.
- Measurement category II is for measurement performed on the circuits directly connected to the low voltage installation.
- Measurement category I is for measurements performed on circuits not directly connected to Mains.

Power Supply



WARNING

- AC Input voltage range: 100V~240V
- Frequency: 50/60Hz
- To avoid electrical shock connect the protective grounding conductor of the AC power cord to an earth ground.

Battery



CAUTION

- Rating: 10.8V, 6 cell Li-ion battery
- Turn off the power and remove the power cord before installing or removing the battery.

Cleaning

- Disconnect the power cord before cleaning.
- Use a soft cloth dampened in a solution of mild detergent and water. Do not spray any liquid.
- Do not use chemicals containing harsh material such as benzene, toluene, xylene, and acetone.

Operation
Environment

- Location: Indoor, no direct sunlight, dust free, almost non-conductive pollution (Note below)
- Temperature: 5°C to 45°C
- Humidity: <90%

(Pollution Degree) EN 61010-1:2010 specifies the pollution degrees and their requirements as follows. The instrument falls under degree 2.

Pollution refers to "addition of foreign matter, solid, liquid, or gaseous (ionized gases), that may produce a reduction of dielectric strength or surface resistivity".

- Pollution degree 1: No pollution or only dry, non-conductive pollution occurs. The pollution has no influence.
- Pollution degree 2: Normally only non-conductive pollution occurs. Occasionally, however, a temporary conductivity caused by condensation must be expected.
- Pollution degree 3: Conductive pollution occurs, or dry, non-conductive pollution occurs which becomes conductive due to condensation which is expected. In such conditions, equipment is normally protected against exposure to direct sunlight, precipitation, and full wind pressure, but neither temperature nor humidity is controlled.

**Storage
environment**

- Location: Indoor
 - Temperature: -20°C to 70°C
 - Humidity: <90%
-

Disposal

Do not dispose this instrument as unsorted municipal waste. Please use a separate collection facility or contact the supplier from which this instrument was purchased. Please make sure discarded electrical waste is properly recycled to reduce environmental impact.

Power cord for the United Kingdom

When using the instrument in the United Kingdom, make sure the power cord meets the following safety instructions.

NOTE: This lead/appliance must only be wired by competent persons




WARNING: THIS APPLIANCE MUST BE EARTHED

IMPORTANT: The wires in this lead are coloured in accordance with the following code:

Green/ Yellow:	Earth
Blue:	Neutral
Brown:	Live (Phase)



As the colours of the wires in main leads may not correspond with the coloured marking identified in your plug/appliance, proceed as follows:

The wire which is coloured Green & Yellow must be connected to the Earth terminal marked with either the letter E, the earth symbol  or coloured Green/Green & Yellow.

The wire which is coloured Blue must be connected to the terminal which is marked with the letter N or coloured Blue or Black.

The wire which is coloured Brown must be connected to the terminal marked with the letter L or P or coloured Brown or Red.

If in doubt, consult the instructions provided with the equipment or contact the supplier.

This cable/appliance should be protected by a suitably rated and approved HBC mains fuse: refer to the rating information on the equipment and/or user instructions for details. As a guide, a cable of 0.75mm² should be protected by a 3A or 5A fuse. Larger conductors would normally require 13A types, depending on the connection method used.

Any exposed wiring from a cable, plug or connection that is engaged in a live socket is extremely hazardous. If a cable or plug is deemed hazardous, turn off the mains power and remove the cable, any fuses and fuse assemblies. All hazardous wiring must be immediately destroyed and replaced in accordance to the above standard.

GETTING STARTED

This chapter provides a brief overview of the GSP-9300, the package contents and an introduction to the front panel, rear panel and GUI.



GSP-9300 Introduction	8
Main Features	8
Accessories	11
Appearance	12
GSP-9300 Front Panel	12
Rear Panel	17
Display	20
Status Icon Overview	23

GSP-9300 Introduction

The GSP-9300 builds on the strong feature set of the GSP-930 and significantly increases performance in almost every aspect; making this the most comprehensive and feature-rich spectrum analyzer GW Instek has released.

Like the GSP-930, the GSP-9300 features a split window display to view data in spectrum, topographic or spectrographic views. There are also a number of additional test functions such as 2FSK, 1PdB and new dedicated EMC pretest functions for EMI and EMS testing. Lastly, the GSP-9300 significantly reduces the sweep time and RBW filter step resolution and complexity.

Main Features

Performance	<ul style="list-style-type: none">• 9kHz~3GHz bandwidth• 1Hz resolution• Nominal RBW accuracy of $\pm 5\%$ <1MHz, $\pm 8\%$ =1MHz• Video bandwidth 1Hz~1MHz (1-3-10 steps)• Amplitude measurement range: DANL~30dBm (frequency dependent)• Input attenuation: 0 ~ 50dB, 1dB steps• Phase noise: < -88dBc/Hz@1GHz, 10kHz, typical
-------------	--

Features	<ul style="list-style-type: none">• 1-3-10 step increments for RBW bandwidth• Three display modes: Spectrum, Topographic and Spectrographic• Split window display• Built-in EMI filter• Auto Wake-up• Built-in preamplifier
----------	--

- Gate sweep
 - Marker Frequency counter
 - Two operating modes: Spectrum and Power Meter mode
 - EMI Pretest functions
 - SEM measurement
 - ACPR measurement
 - OCBW measurement
 - 2FSK measurement
 - Phase jitter measurement
 - Harmonics measurement
 - P1dB measurement
 - Channel power measurement
 - Demodulation analyzer
 - Diverse marker functions and features with Peak Table
 - Sequence function to automatically perform pre-programmed sequential operations
 - Optional battery operation
-

Interface


- 8.4 color LCD (800×600)
- On-screen menu icons
- DVI-I video output
- RS-232 with RTS/CTS hardware flow control
- USB 2.0 with support for USB TMC
- LAN TCP/IP with LXI support
- Optional GPIB/IEEE488 interface
- Optional 3G USB adapter for WLAN
- Optional power meter adapter
- IF output @ 886MHz
- Headphone output
- REF (reference clock) input/output BNC ports
- Alarm/Open collector output BNC port
- Trigger/Gate input BNC ports
- RF N-type input port
- Tracking generator output
- DC +7V/500mA output SMB port

Accessories



Standard Accessories	Part number	Description
	Region dependant	User manual
	Region dependant	Power cord
	N/A	Certificate of calibration
	N/A	Quick Start Manual
	N/A	User Manual CD
Options	Option number	Description
	Opt1.	Tracking generator
	Opt2.	Battery (11.1V/5200mAH Li-ion battery)
	Opt3.	GPIO interface (IEEE 488 bus)
Optional Accessories	Part number	Description
	GSC-009	Soft Carrying Case
	PWS-06	USB Average Power Sensor (up to 6200 MHz; -32 to 20 dBm)
	GRA-415	6U Rack mount kit
Software Downloads		
	PC Software for Windows System	
	IVI Driver Supports LabView & LabWindows/CVI Programming	
	Android System (“GSP-9300 Remote Control”, available on Google Play.)	


Appearance











GSP-9300 Front Panel














LCD display	800×600 color LCD display. The display shows the soft keys for the current function, frequency, amplitude and marker information.
-------------	---

Function keys	 ~ 	The F1 to F7 function keys directly correspond to the soft keys on the right-hand side of display.
---------------	---	--

Main keys		Sets the center frequency, start frequency, stop frequency, center frequency step and frequency offset values.
-----------	---	--

		Sets the span, with options for full span, zero span and last span.
		Sets the amplitude reference level, attenuation, pre-amplifier controls, scale and other options for attenuation and scale.
		Automatically searches the peak signal with maximum amplitude and displays it with appropriate horizontal and vertical scales.
Control keys		Sets the resolution bandwidth, video bandwidth, average type and turns the EMI filter on/off.
		Sets the sweep time and gate time.
		Toggles the Sweep Control between <i>Fast</i> and <i>Normal</i> mode.
		Accesses measurement options such as ACPR, OCBW, demodulation measurements, SEM, TOI, 2FSK, phase jitter and other advanced measurements.
		Dedicated EMI testing and setup menu.
		Sets traces and trace related functions.
		Sets and tests Pass/Fail limit lines.


		The Display key configures the windowing mode and basic display properties.
		Sets the triggering modes.
File		File utilities options
		Save the trace, state etc., and save options.
		Recall the trace, state etc., and recall options.
Marker		Turns the Markers on/off and configures the markers.
		The <i>Marker</i> ► key positions the markers on the trace.
		Finds each maximum and minimum peak. Used with the Marker function.
Auxiliary		Access, set and edit program sequences.
		The <i>Option Control</i> key allows you to setup optional accessories such as the Tracking Generator, Power Meter or Demo Kit.
		The System key shows system information, settings and other system related functions.

Preset / Local key



The *Preset* key will restore the spectrum analyzer to the Factory or User Preset settings.

The Preset key will also return the instrument back to local control after it has been in remote control mode.




The Quick Save utility allows you to save either the state, trace, display screen, limit line, correction or sequence with only a single press.

Power key




Turns the instrument on/off. On = yellow, off = blue.

Scroll wheel




Edit values, select listed items.

Arrow keys



Increment/decrement values (in steps), select listed items.


RF input terminal



RF input port. Accepts RF inputs.

- Maximum input: +30dBm
- Input impedance: 50Ω
- Maximum DC voltage: ±50V
- N-type: female


DC power supply



SMB port supplies power for optional accessories.


- DC +7V
- 500mA Max.

Numeric keypad



The numeric keypad is used to enter values and parameters. It is often used in conjunction with the arrow keys and scroll wheel.

TG output port



The Tracking Generator (TG) output source.


- N-type: female
- Input impedance: 50Ω
- Output power: -50dBm to 0dBm
- Maximum reversed power: +30dBm

USB A, Micro SD




USB A port, Micro SD port for saving/recalling settings/files.

Rear Panel



RS232




RS232 9 pin DSUB port.

IF OUT



SMA IF Out port.


DVI-I



DVI video out port. Supports SVGA (800X600) @ 60Hz.


Fan

Power Socket




Power Socket:
100~240V, 50/60Hz.

Battery pack




Voltage: 10.8V
Capacity: 5200mAH

REF IN



BNC female reference input.

REF OUT



BNC female reference output:
10MHz, 50 Ω impedance

Security Lock




ALARM OUT



BNC female open collector Alarm
output.

TRIG IN/GATE IN



BNC female 3.3V CMOS trigger
input/gated sweep input.

Phone



3.5mm stereo headphone jack
(wired for mono operation)

USB B




USB B Device port. USB 1.1/2.0

LAN










RJ-45 10Base-T/100Base-Tx

Display

























Scale	Displays the vertical scale of the vertical grid.
Reference level	Displays the reference level.
Attenuation	Displays the vertical scale (attenuation) of the input signal.
Date/Time	Displays the date and time.
Marker information	Displays marker information.
LXI icon	This icon indicates the status of the LXI connection. For details, see page 27.

Function menu	Soft menu keys associated with the F1 to F7 function keys to the right of the display.	
Sweep Mode		This icon displays the sweep mode, as set by the Sweep Mode key.
Sweep settings		Sweep icon that shows the sweep status.
Trace and detection settings		Trace icon that shows the trace type and the detection mode used for each trace.
Blank		Unassigned setting icons.
Trigger settings		Trigger icon that shows the trigger status.
Pre-amp settings		Pre-amplifier icon that shows the Pre-amplifier status.
USB settings		Displays the status of the USB A port.
Status Icons	Displays the interface status, power source status and alarm status, etc. See the Status Icon Overview on page 23 for a list of the status icons.	
Frequency/ Bandwidth settings	Displays the Start, Center and Stop frequencies, RBW, VBW, Span and Sweep settings.	

Entry/Message area	This area is used to show system messages, errors and input values/parameters.
Trace and waveforms	Main display showing the input signals, traces, limit lines and marker positions.
Sweep progress bar	The sweep progress bar shows the progress of slow sweeps (greater than 2 seconds).

Status Icon Overview

3G Adapter		Indicates that the 3G adapter is installed and turned on.
Demo Kit		Indicates that the demo kit is installed and turned on.
PreAmp		Indicates that the pre amplifier is on.
AC		Shown when running on AC power.
AC Charge		Shown when the AC power is charging the battery.
Alarm Off		Alarm buzzer output is currently off.
Alarm On		Alarm buzzer output is currently on.
Amplitude Offset		Indicates that the amplitude-shift is active. This icon appears when amplitude-related functions are used: Reference level offset Amplitude Correction Input Z = 75Ω & Input Z cal >0
Battery indicator	 ~ 	Indicates the battery charge.
Bandwidth Indicator		Indicates that the RBW or VBW settings are in manual mode.

Average		Indicates that the Average function is active.
External Lock		Indicates that the system is now locked and refers to the external reference input signal
External Trigger		External trigger signal is being used.
Math		Trace math is being used.
Sequence Indicator		Shown when a sequence is running.
Sweep Indicator		Indicates that the sweep time is manually set.
Tracking generator		Indicates that the tracking generator is turned on.
TG Normalization		Indicates that the tracking generator has been normalized.
Wake-up clock		Indicates that the wake-up clock is turned on.
USB		Indicates that a USB flash drive is inserted into the front panel and is recognized.
Micro SD		Indicates that a micro SD card is inserted into the front panel and is recognized.

REMOTE CONTROL

This chapter describes the basic configuration of IEEE488.2 based remote control. This chapter includes interface configuration, a remote control overview as well as the control syntax and commands.


Interface Configuration	26
Command Syntax	49
Status Registers	54
Command List.....	64

Interface Configuration

Configure to USB Remote Interface

USB configuration	PC side connector	Type A, host
	GSP side connector	Rear panel Type B, slave
	Speed	1.1/2.0 (full speed/high speed)
	USB Class	USB TMC (USB T&M class)

- Panel operation
1. Connect the USB cable to the rear panel USB B port.

2. Press  >More[F7]>RmtInterface Config[F1]>USB Mode and toggle the USB mode to Device.



Note

It may take a few moments to switch USB modes.

Configure GPIB Interface


To use GPIB, the optional GPIB port must be installed.

- Configure GPIB
1. Ensure the spectrum analyzer is off before proceeding.

2. Connect a GPIB cable from a GPIB controller to the GPIB port on the spectrum analyzer.

3. Turn the spectrum analyzer on.



4. Press  >More[F7]>RmtInterface
Config[F1]>GPIB Addr[F1] and set the GPIB
address.

GPIB address 0~30

- GPIB constraints
- *Maximum 15 devices altogether, 20m cable length, 2m between each device*
 - *Unique address assigned to each device*
 - *At least 2/3 of the devices turned On*
 - *No loop or parallel connection*

Configure the LAN and LXI Interface

The GSP-9300 is a class C LXI compliant instrument. The LXI specification allows instrumentation to be configured for remote control or monitoring over a LAN or WLAN. The GSP-9300 also supports HiSlip. HiSlip (High-Speed LAN Instrument Protocol) is an advanced LAN based standard for 488.2 communications.

For details on the LXI specification and compliance classes, please see the LXI website @ <http://www.lxistandard.org>.


Background	The LAN interface is used for remote control over a network. The spectrum analyzer supports DHCP connections so the instrument can be automatically connected to an existing network. Alternatively, network settings can also be manually configured.
------------	--

LAN configuration Settings	IP Address	Default Gateway
	Subnet Mask	DNS Server
	DHCP on/off	

Connection	Connect an Ethernet cable from the network to the rear panel LAN port.
------------	--



Settings

1. Press  > More[F7] > RmtInterface[F1] > LAN[F2] > LAN Config[F1] to set the LAN settings:

IP Address[F1] Sets the IP address.

Subnet Mask[F2] Sets the subnet mask.

Default

Gateway[F3] Sets the default gateway.

DNS Server[F4] Sets the DNS server address

LAN Config[F5] Toggles the LAN configuration between DHCP and manual settings.

Hint: Use dotted decimal notation when entering IP addresses, ie., 172.16.20.8

2. Press *Apply[F6]* to confirm the LAN configuration settings.

Display Icon





The LXI icon turns green when connected to a LAN and will flash if the "Identification" setting is on, see page 37.

Set Password

The password on the LXI webpage can be set from the spectrum analyzer. The password is shown in the system information.


By default the password is set to: lxiWNpwd

3. Press  > More[F7] > RmtInterface Config[F1] > LAN[F2] > LXIPassword[F3] to set the password.
4. Enter the password using the F1~F7 keys, as shown below, or use the numeric keypad to enter numbers:




Limitations:

- *No spaces*
- *Only 1~9, A~Z, a~z characters allowed*



Menu tree to enter the password

5. The password appears on the bottom of the screen as it is created.





6. Press **Enter** to confirm setting the password.

Hi SLIP Port

7. Press **System** > More[F7] > RmtInterface Config[F1] > LAN[F2] > HiSLIPPort to see the Hi Slip Port number.
HiSlip port 4880

Reset LAN It may be necessary to reset the LAN configuration settings before the LAN can be used.

8. Press  >More[F7]>RmtInterface Config[F1]>LAN Reset[F3] to reset the LAN.
9. The GSP-9300 will now automatically reboot.
-

 **Note** Each time the LAN is reset, the default password is restored.

Default password: lxiWNpwd

Configure the WLAN Interface


The WLAN settings operate using any standard 3G USB modem. For remote locations, using a 3G modem allows you to access the GSP-9300 web server or to control the GSP-9300 via remote control commands.


Background To use the GSP-9300 as a server using a 3G modem, you must first obtain a fixed IP address from a network provider. Each provider will assign different fixed IP addresses.



WLAN configuration Settings	IP Address	Default Gateway
	Subnet Mask	DNS Server

Connection


Connect the 3G USB modem to the front panel USB A port.

The 3G status icon  will appear when the 3G USB adapter is connected. When it is first connected it will be grayed-out to indicate that it is connected but not activated.


Settings

1. Insert the 3G USB modem into the front panel USB A port and wait for the 3G USB  icon to appear.
2. Press  > More[F7] > RmtInterface[F1] > LAN[F2] > WLAN Config[F2] > Apply[F6] and wait for the 3G USB modem to establish the WLAN settings.

“Finish!!!”, is shown when the configuration is complete.
3. The network settings will be displayed in the System menu icons.



Display Icon




The 3G USB icon turns green when a successful connection has been made.

Set Password

The password on the LXI webpage can be set from the spectrum analyzer. The password is shown in the system information.


By default the password is set to: lxiWNpwd

4. Press **System** > More[F7] > RmtInterface Config[F1] > LAN[F2] > LXIPassword[F3] to set the password.
5. Enter the password using the F1~F7 keys, as shown below, or use the numeric keypad to enter numbers:



Limitations:

- No spaces
- Only 1~9, A~Z, a~z characters allowed




Menu tree to enter the password


6. The password appears on the bottom of the screen as it is created.



Password

7. Press  to confirm setting the password.


Hi SLIP Port

8. Press  > More[F7] > RmtInterface Config[F1] > LAN[F2] > HiSLIPPort to see the Hi Slip Port number.

HiSlip port 4880

Reset LAN

It may be necessary to reset the LAN configuration settings before the LAN can be used.

9. Press  >More[F7]>RmtInterface Config[F1]>*LAN Reset*[F3] to reset the LAN.

10. The GSP-9300 will now automatically reboot.
-





Note

Each time the LAN is reset, the default password is restored.

Default password: lxiWNpwd

Configure RS232C

Background	The RS232C interface is used for remote control with a PC.	
RS232C Configuration settings	Baud Rate	Stop bit: 1 (fixed)
	Parity: none (fixed)	Data bit: 8 (fixed)
Connection	Connect an RS232C cable from the PC to the rear panel RS232 port.	

1. Press  > More[F7] > RmtInterface Config[F1] > RS232 BaudRate[F4] to set the baud rate.
- | | | |
|--------|-------|-------|
| 300 | 600 | 1200 |
| 2400 | 4800 | 9600 |
| 19200 | 38400 | 57600 |
| 115200 | | |

RS232C Remote Control Function Check

Functionality check	Invoke a terminal application such as Realterm.
	To check the COM port No, see the Device Manager in the PC. For WinXP; Control panel → System → Hardware tab.
	Run this query command via the terminal after the instrument has been configured for RS232 remote control (page 35).
	*idn?
	This should return the Manufacturer, Model

number, Serial number, and Firmware version in the following format.

- *GWINSTEK,GSP9300,XXXXXXXX,T.X.X.X.X*

Manufacturer: GWINSTEK

Model number : GSP9300

Serial number : XXXXXXXX

Firmware version : T.X.X.X



Note

For further details, please see the programming manual, available on the GW Instek web site @ www.gwinstek.com.

LXI Browser Interface and Function Check

Functionality
check


Enter the IP address of the spectrum analyzer in a web browser after the instrument has been configured and connected to the LAN (page 27) or WLAN (page 30).

http:// XXX.XXX.XXX.XXX

The web browser interface appears:

Welcome Page

The Welcome Page lists all the LXI and LAN/WLAN configuration settings as well as the instrument identification. The instrument identification can be disabled from this page.



Note



The LXI icon on the GSP-9300 display will flash when the Identification setting is turned on.

View & Modify Configuration

The View & Modify Configuration allows you to modify the LAN settings from the browser.

Press the *Modify Configuration* button to modify any of the configuration files.

A password must be entered to alter the settings.

Default password: lxiWNpwd
[Note: password is case sensitive.]



Note

If the “Factory Defaults” option is chosen, the password will be reset back to the default password


It will also be necessary to manually reset the spectrum analyzer when a message prompts you to do so on the web browser.

SCPI Command

The SCPI Command page allows you to enter SCPI commands directly from the browser for full remote control. Please see the programming manual for details. A password must be entered before remote commands can be used.


Default password: lxiWNpwd

[Note: password is case sensitive.]



Get Image

The Get Image page allows the browser to remotely capture a screenshot of the GSP-9300 display.



Note

For further details, please see the programming manual, available on the GW Instek web site @ www.gwinstek.com.


GPIB Function Check

Background	To test the GPIB functionality, National Instruments Measurement and Automation Explorer can be used. This program is available on the NI website, www.ni.com , via a search for the VISA Run-time Engine page, or “downloads” at the following URL, http://www.ni.com/visa/
------------	--


Requirements	Operating System: Windows XP, 7, 8
--------------	------------------------------------

Functionality check	<ol style="list-style-type: none"> 1. Start the NI Measurement and Automation Explorer (MAX) program. Using Windows, press:
---------------------	--


Start>All Programs>National Instruments>Measurement & Automation




2. From the Configuration panel access;
My System>Devices and Interfaces>GPIBX>
3. Press *Scan for Instruments*.




4. Select the device (GPIB address of GSP-9300) that now appears in the *System>Devices and Interfaces > "GPIBX" >"Instrument X"* node.
5. Click on the *VISA Properties* tab on the bottom.
6. Click *Open Visa Test Panel*.



7. Click on *Configuration*.
8. Click on the *GPIB Settings* tab and confirm that the GPIB settings are correct.



9. Click on the *I/O Settings* tab.
10. Make sure the *Enable Termination Character* check box is checked, and the terminal character is \n (Value: xA).
11. Click *Apply Changes*.



12. Click on *Input/Output*.
13. Click on the *Basic/IO* tab.

14. Enter *IDN? in the *Select or Enter Command* drop down box.
15. Click *Query*.
16. The *IDN? query will return the Manufacturer, model name, serial number and firmware version in the dialog box.

GWINSTEK,GSP9300,ENXXXXXX,TX.X.X.X



USB Function Check

Background To test the USB functionality, National Instruments Measurement and Automation Explorer can be used. This program is available on the NI website, www.ni.com, via a search for the VISA Run-time Engine page, or “downloads” at the following URL, <http://www.ni.com/visa/>

In addition the IVI driver for the GSP-9300 must also be downloaded. The IVI driver can also be downloaded from the NI website with a search for the GSP-9300 in the thirdparty drivers section.

<http://www.ni.com/downloads/instrument-drivers/>


Requirements Operating System: Windows XP, 7, 8

Functionality check

1. Set the Remote interface to USB, see page 26.
2. From the Windows Device Manager sure the IVI driver recognizes the USB connection. The GSP-9300 will be recognized as a USB Test and Measurement device (IVI) when the connection is successful.


If the connection is not recognized, reinstall the IVI driver and set the interface to USB again.

To access the Device Manager in Windows 7:
Start>Control Panel>Hardware and Sound>Device Manager




3. Start the NI Measurement and Automation Explorer (MAX) program. Using Windows, press:


Start>All Programs>National Instruments>Measurement & Automation



4. Select the GSP-9300 device that now appears in the *System>Devices and Interfaces > GSP9300"USBX..."* node.
5. Click on the *VISA Properties* tab on the bottom.
6. Click *Open Visa Test Panel*.



7. Click on the *I/O Settings* tab.
8. Make sure the *Enable Termination Character* check box is checked, and the terminal character is \n (Value: xA).
9. Click *Apply Changes*.



10. Click on *Input/Output*.
11. Click on the *Basic/I/O* tab.
12. Enter **IDN?* in the *Select or Enter Command* drop down box.
13. Click *Query*.
14. The **IDN?* query will return the Manufacturer, model name, serial number and firmware version in the dialog box.

GWINSTEK,GSP9300,ENXXXXXX,TX.X.XX




Command Syntax

Compatible Standard	IEEE488.2	Full compatibility
	SCPI, 1999	Full compatibility

Command Structure

SCPI (Standard Commands for Programmable Instruments) commands follow a tree-like structure, organized into nodes. Each level of the command tree is a node. Each keyword in a SCPI command represents each node in the command tree. Each keyword (node) of a SCPI command is separated by a colon (:).

For example, the diagram below shows an SCPI sub-structure and a command example.



Command types

There are a number of different instrument commands and queries. A command sends instructions or data to the unit and a query receives data or status information from the unit.

Command types

Simple	A single command with/without a parameter
Example	*RST

Query	A query is a simple or compound command followed by a question mark (?). A parameter (data) is returned.
-------	--

Example	CALCulate:CSO:STATe?
---------	----------------------

Compound	Two or more commands on the same command line. Compound commands are separated with either a semi-colon (;) or a semi-colon and a colon (;:).
----------	---

A semi-colon is used to join two related commands, with the caveat that the last command must begin at the last node of the first command.

A semi-colon and colon are used to combine two commands from different nodes.

Example	calc:ctb:stat on;result?
---------	--------------------------

Command Forms

Commands and queries have two different forms, long and short. The command syntax is written with the short form of the command in capitals and the remainder (long form) in lower case.

The commands can be written in capitals or lower-case, just so long as the short or long forms are complete. An incomplete command will not be recognized.

Below are examples of correctly written commands.


Long form	CALCulate:ACPR:STATe? calculate:acpr:state? CALCULATE:ACPR:STATE?
Short form	CALC:ACPR:STAT? calc:acpr:stat?

Square Brackets

Commands that contain square brackets indicate that the contents are optional. The function of the command is the same with or without the square bracketed items, as shown below.

Both “:OUTPut[:STATe]?” and “:OUTPut?” are both valid forms.

Command Format



- | | |
|-------------------|--|
| 1. Command header | 4. Comma (no space before/after comma) |
| 2. Space | |
| 3. Parameter 1 | 5. Parameter 2 |

Common Input Parameters	Type	Description	Example
	<Boolean>	Boolean logic	0, 1
	<NR1>	integers	0, 1, 2, 3
	<NR2>	decimal numbers	0.1, 3.14, 8.5
	<NR3>	floating point	4.5e-1, 8.25e+1
	<NRf>	any of NR1, 2, 3	1, 1.5, 4.5e-1
	<freq>	Input: <NRf> + unit Unit = kHz, MHz, GHz. Note: The unit can be omitted (unit defaults to Hz). Return: <NR3>	2.5 mhz 2.5e+5
		Note: Units = Hz.	
	<limit num>	<NR1>	
	<point>	<NR1>	
	<offset>	Input: <NRf> + unit Note: The unit can be omitted (unit defaults to dB). Return: <NR3>	30 db 3.0e+1
		Note: Units = dB.	
	<rel_ampl>	Input: <NRf> + unit Note: The unit can be omitted (unit defaults to dB). Return: <NR3>	20 db 2.0e+1

Note: Units = dB.

<ampl> Input: 30 mv
 NR3 +unit type

Note: The unit can be omitted.
 (Unit defaults to current y-axis unit).

Return:
 <NR3> 3.0e-2

Note: Units = current y axis unit.

<trace name> <NR1> trace1

<time> Input:
 <NR3> + unit 2.3e-6 ms

Unit = ms, ns, ps, ks
 Note: The unit can be omitted
 (unit defaults to seconds).

Return:
 <NR3> 3.0e-2

Note: Units = seconds.


<ip address> <String> 172.16.20.20

Message Terminator	LF	Line feed code (0x0A)
--------------------	----	-----------------------


Status Registers

Status Registers Overview ---

Description	<p>The status registers are used to determine the status of the spectrum analyzer. The status registers maintain the status of the pass/fail limits, trigger status and other operation statuses.</p> <p>The status registers are arranged in a number of groups:</p> <ul style="list-style-type: none">• <i>Questionable Status Registers</i>• <i>Standard Event Status Registers</i>• <i>Operation Status Registers</i>• <i>Status Byte Register</i>• <i>Service Request Enable Register</i>• <i>Error/Event Queue</i>• <i>Output Buffer</i>
-------------	--



Status Register Structure	<p>Each status register (excluding the status byte register) is divided into a number of register structures:</p> <ul style="list-style-type: none">• <i>Condition register</i>• <i>Positive transition register</i>• <i>Negative transition register</i>• <i>Event Register</i>• <i>Event Enable Register</i>
Condition Registers	<p>The condition registers report the state of the GSP-9300. Condition registers can only be read.</p>
PTR Registers	<p>The positive transistion registers are used to filter for events that occur from a negative to a positive transition.</p>
NTR Registers	<p>The negative transition registers are used to filter for events that occur from a positive to negative transistion.</p>
Event Registers	<p>The PTR/NTP registers dictate the type transistion conditions that will set the corresponding bits in the event registers. The event registers can only be read. Reading an event register will clear it.</p>
Event Enable Registers	<p>The event enable registers determine which events in the corresponding event registers will set the summary bits in a higher-order register.</p>



Status Byte Register (STB)

Overview

The Status Byte register consolidates the status events of all the status registers. The Status Byte register can be cleared with the *CLS command.

Any bits set in the Status byte register acts as a summary register for all the other status registers and indicates if there is a service request, an error in the Error Queue or data in the Output Queue. Reading the Status Byte register will reset the register to 0.

The Service Request Enable Register controls which bits in the Status Byte Register are able to generate service requests.

Bit Summary	Bit	Weight	Description
	2	4	Error/Event Queue Summary bit: This bit is set when there is a message in the error queue.
	3	8	Questionable Status Summary Bit: This is the summary bit for the Questionable Status Register.
	4	16	MAV: This bit is set when there is a message in the output queue.

5	32	ESB: This is the summary bit for the Standard Event Register.
6	64	MSS/RQS: The MSS bit is the summary bit for the Service Request Enable Register. The RQS bit is set to 1 when the MSS bit is set to 1.
7	128	Operation Status Summary Bit: This is the summary bit for the Operation Status Register.

Standard Event Status Register (ESR)

Overview The Standard Event Status Register Group indicates if any errors have occurred or fail limits tripped. Reading this register will clear the register.

Bit Summary	Bit	Weight	Description
	2	4	Query Error: When a query error has occurred, this bit is set to 1.
	3	8	Device-Specific Error: When a device dependent error has occurred, this bit is set to 1.
	4	16	Execution Error: When an execution error has occurred, this bit is set to 1.
	5	32	Command Error: When a command error has occurred, this bit is set to 1.
	6	64	User Request: When a panel key is pressed, this bit is set to 1.
	7	128	Power On: When the instrument is turned off → on, this bit is set to 1.

Operation Status Register

Overview The Operation Status Register Group indicates the operating status of the GSP-9300.

Bit Summary	Bit	Weight	Description
	3	8	Sweeping: Indicates that a sweep is in progress.
	4	16	Measuring: The instrument is currently performing a measurement.
	5	32	Waiting for Trigger: The instrument is in a “wait for trigger” state.

Questionable Status Register

Overview The Questionable Status Register Group indicates if any limits have been tripped.

Bit Summary	Bit	Weight	Description
	5	32	Frequency Status Summary Bit: This is the summary bit of the Frequency Status Register.
	8	256	Uncal: This bit is set when a signal level occurs because the sweep is too fast.
	9	512	Limit fail: This bit is set to 1 when the limit line has been violated.
	10	1024	ACP Limit Status Summary Bit: This is the summary bit for the ACP Limit Status Register.
	11	2048	SEM Limit Status Summary Bit: This is the summary bit for the SEM Limit Status Register.
	12	4096	TOI Limit Status Summary Bit: This is the summary bit for the TOI Limit Status Register.
	13	8192	Pmet Limit Fail: This bit is set to 1 when the power meter limit has been violated.

- | | | |
|----|-------|--|
| 14 | 16384 | 2FSK Fail: This bit is set to 1 when the 2FSK fail conditions are met. |
| 15 | 32768 | Demod Fail: This is the summary bit for the Demod Fail Register. |

Questionable Status Frequency Register

Overview The Questionable Status Frequency Register indicates if the span or BW settings are invalid.

Bit Summary	Bit	Weight	Description
	5	32	Invalid Span or BW: This bit is set to 1 when there is an invalid span or bandwidth (setting) during the frequency count.

Questionable Status ACP Limit Register

Overview The Questionable Status ACP Limit Register Group indicates if any adjacent channel limits have been tripped.

Bit Summary	Bit	Weight	Description
	0	1	Main Channel High Fail: This bit is set to 1 when the Main CH HLimit has been violated.
	1	2	Main Channel Low Fail: This bit is set to 1 when the Main CH LLimit has been violated.
	2	4	Adj1 High Fail: This bit is set to 1 when the ADJCH 1 HLimit has been violated.
	3	8	Adj1 Low Fail: This bit is set to 1 when the ADJCH 1 LLimit has been violated.
	4	16	Adj2 High Fail: This bit is set to 1 when the ADJCH 2 HLimit has been violated.
	5	32	Adj2 Low Fail: This bit is set to 1 when the ADJCH 2 LLimit has been violated.
	6	64	Adj3 High Fail: This bit is set to 1 when the ADJCH 3 HLimit has been violated.
	7	128	Adj3 Low Fail: This bit is set to 1 when the ADJCH 3 LLimit has been violated.

Questionable Status SEM Limit Register

Overview

The Questionable Status SEM Limit Register Group indicates if any of the SEM offset limits have been tripped.

Bit Summary	Bit	Weight	Description
	0	1	Offset 1 Upper Fail: This bit is set to 1 when the SEM Offset 1 upper limit has been violated.
	1	2	Offset 1 Lower Fail: This bit is set to 1 when the SEM Offset 1 lower limit has been violated.
	2	4	Offset 2 Upper Fail: This bit is set to 1 when the SEM Offset 2 upper limit has been violated.
	3	8	Offset 2 Lower Fail: This bit is set to 1 when the SEM Offset 2 lower limit has been violated.
	4	16	Offset 3 Upper Fail: This bit is set to 1 when the SEM Offset 3 upper limit has been violated.
	5	32	Offset 3 Lower Fail: This bit is set to 1 when the SEM Offset 3 lower limit has been violated.
	6	64	Offset 4 Upper Fail: This bit is set to 1 when the SEM Offset 4 upper limit has been violated.
	7	128	Offset 4 Lower Fail: This bit is set to 1 when the SEM Offset 4 lower limit has been violated.
	8	256	Offset 5 Upper Fail: This bit is set to 1 when the SEM Offset 5 upper limit has been violated.
	9	512	Offset 5 Lower Fail: This bit is set to 1 when the SEM Offset 5 lower limit has been violated.

Questionable Status TOI Limit Register

Overview The Questionable Status TOI Limit Register Group indicates if the 3rd Order Upper or Lower limit has been tripped.

Bit Summary	Bit	Weight	Description
	0	1	3rd Upper Fail: This bit is set to 1 when the 3rd Order Upper limit has been tripped.
Bit Summary	1	2	3rd Lower Fail: This bit is set to 1 when the 3rd Order Lower limit has been tripped.

Questionable Status Demod Fail Register

Overview The Questionable Status Demod Fail Register Group indicates if pass/fail limit has been tripped for either AM or FM analysis.

Bit Summary	Bit	Weight	Description
	0	1	AM Fail: This bit is set to 1 when the limit has been tripped for AM depth, carrier offset or carrier power.
Bit Summary	1	2	FM Fail: This bit is set to 1 when the limit has been tripped for FM frequency deviation, carrier offset or carrier power.

Command List

SCPI Commands	*CLS	74
	*IDN?	74
	*ESE	75
	*ESR?	75
	*OPC	75
	*RST	76
	*SRE	76
	*STB?	76
	*TST?	76
	*WAI	77

CALCulate	:CALCulate:ACPR:ACHannel<n>:HLIMit:FAIL?	79
Commands	:CALCulate:ACPR:ACHannel<n>:LLIMit:FAIL?	80
	:CALCulate:ACPR:ACHannel<n>:LOWer?	80
	:CALCulate:ACPR:ACHannel<n>:UPPer?	80
	:CALCulate:ACPR:ACHannel<n>:STATe	81
	:CALCulate:ACPR:CHANnel:HLIMit:FAIL?	81
	:CALCulate:ACPR:CHANnel:LLIMit:FAIL?	82
	:CALCulate:ACPR:CHPower?	82
	:CALCulate:ACPR:STATe	82
	:CALCulate:BFSK:STATe	83
	:CALCulate:BFSK:REStart	83
	:CALCulate:BFSK:RESult?	83
	:CALCulate:CNR:RESult?	84
	:CALCulate:CNR:STATe	84
	:CALCulate:CSO:RESult?	84
	:CALCulate:CSO:STATe	85
	:CALCulate:CTB:RESult?	85
	:CALCulate:CTB:STATe	85
	:CALCulate:CTB:REStart	86
	:CALCulate:DELTamarker<n>:PAIR:SPAN	86
	:CALCulate:DELTamarker<n>:PAIR:CENTer	86
	:CALCulate:DELTamarker<n>:X	86
	:CALCulate:DELTamarker<n>:Y?	87
	:CALCulate:DEMod:AM:RESult:CURRent?	87
	:CALCulate:DEMod:AM:RESult:MINimum?	88
	:CALCulate:DEMod:AM:RESult:MAXimum?	88

:CALCulate:DEMod:AM:STATe	88
:CALCulate:DEMod:EARPhone:STATe.....	89
:CALCulate:DEMod:FM:RESult:CURRent?	89
:CALCulate:DEMod:FM:RESult:MINimum?	90
:CALCulate:DEMod:FM:RESult:MAXimum?	90
:CALCulate:DEMod:FM:STATe.....	91
:CALCulate:DEMod:RESet	91
:CALCulate:HARMonic:DISToRtion?	91
:CALCulate:HARMonic:RESult?.....	92
:CALCulate:HARMonic:STATe	92
:CALCulate:JITTer:STATe.....	92
:CALCulate:JITTer:CARRier:POWer?	93
:CALCulate:JITTer:PHASe?	93
:CALCulate:JITTer:TIME?	93
:CALCulate:LIMit<n>:CLEar	94
:CALCulate:LIMit<n>:DATA	94
:CALCulate:LIMit:FAIL?.....	94
:CALCulate:LIMit:LOW	95
:CALCulate:LIMit:HIGH	95
:CALCulate:LIMit<n>:MARKer	95
:CALCulate:LIMit:MODE	96
:CALCulate:LIMit:STATe	96
:CALCulate:LIMit<n>:TRACe	96
:CALCulate:LIMit:TYPE.....	97
:CALCulate:MARKer:AOff	97
:CALCulate:MARKer<n>:FCount:RESolution	97
:CALCulate:MARKer<n>:FCount:RESolution	
:AUTO	98
:CALCulate:MARKer<n>:FCount:STATe	98
:CALCulate:MARKer<n>:FCount:X?	99
:CALCulate:MARKer<n>:NOISe:STATe	99
:CALCulate:MARKer<n>:NOISe:Y?	100
:CALCulate:MARKer<n>:PEAK.....	100
:CALCulate:MARKer:PEAK:CTRAck:STATe	100
:CALCulate:MARKer:PEAK:DATA?	101
:CALCulate:MARKer:PEAK:EXCURsion	101
:CALCulate:MARKer:PEAK:SORT:TYPE.....	102
:CALCulate:MARKer:PEAK:TABLE:STATe	102
:CALCulate:MARKer:PEAK:THReshold.....	102
:CALCulate:MARKer:PEAK:THReshold:STATe	103
:CALCulate:MARKer<n>:SET.....	103
:CALCulate:MARKer<n>:STATe.....	104
:CALCulate:MARKer:TABLE:STATe	104

	:CALCulate:MARKer<n>:TRACe	104
	:CALCulate:MARKer<n>:TRACe:AUTO	105
	:CALCulate:MARKer<n>:TYPE	105
	:CALCulate:MARKer<n>:X	106
	:CALCulate:MARKer<n>:Y?	106
	:CALCulate:MATH:PDIF	106
	:CALCulate:MATH:LDIF	107
	:CALCulate:MATH:LOFF	107
	:CALCulate:NDB:STATe	107
	:CALCulate:NDB:BANDwidth BWIDth?	108
	:CALCulate:NORMalize:STATe	108
	:CALCulate:OCBW:STATe	109
	:CALCulate:OCBW:BANDwidth BWIDth?	109
	:CALCulate:OCBW:CHPower?	109
	:CALCulate:OCBW:POWer?	110
	:CALCulate:OCBW:PSD?	110
	:CALCulate:P1DB:STATe	110
	:CALCulate:P1DB:GAIN:AVERAge?	111
	:CALCulate:P1DB:GAIN:RESult?	111
	:CALCulate:P1DB:RESult?	111
	:CALCulate:PMETer:POWer?	112
	:CALCulate:PMETer:LIMit:STATe	112
	:CALCulate:PMETer:LIMit:FAIL?	112
	:CALCulate:SEM:STATe	113
	:CALCulate:SEM:OFFSet<n>:RESult?	113
	:CALCulate:TOI:DIFFerential?	114
	:CALCulate:TOI:FREQuency:DIFFerential?	114
	:CALCulate:TOI:LIMit:STATe	114
	:CALCulate:TOI:RESult?	115
	:CALCulate:TOI:STATe	115
 CONFigure Commands	:CONFigure:MODE	116
 DISPlay Commands	:DISPlay:BRIGhtness	118
	:DISPlay:ENABle	118
	:DISPlay:DEMod[:WINDow]:TRACe:X[:SCALe]:AUTO	119
	:DISPlay:DEMod[:WINDow]:TRACe:X[:SCALe] :PDIVision	119
	:DISPlay:DEMod[:WINDow]:TRACe:X[:SCALe] :RPOSition	120

	:DISPlay:DEMod[:WINDow]:TRACe:X[:SCALe]	
	:RVALue	120
	:DISPlay:DEMod[:WINDow]:TRACe:Y [:SCALe]:AUTO	
	120
	:DISPlay:DEMod[:WINDow]:TRACe:Y[:SCALe]	
	:PDIVision.....	121
	:DISPlay:DEMod[:WINDow]:TRACe:Y[:SCALe]	
	:RPOSition.....	121
	:DISPlay:DEMod[:WINDow]:TRACe:Y[:SCALe]	
	:RVALue	122
	:DISPlay[:WINDow]:NORMal.....	122
	:DISPlay[:WINDow]:SPECtrogram.....	122
	:DISPlay[:WINDow]:SPLit:NORMal:ALTErnate.....	123
	:DISPlay[:WINDow]:SPLit:NORMal:ACTive	123
	:DISPlay[:WINDow]:SPLit:SPECtrogram	123
	:DISPlay[:WINDow]:SPLit:TOPO	123
	:DISPlay[:WINDow]:TOPO.....	124
	:DISPlay[:WINDow]:TOPO:MARK:PERCent?.....	124
	:DISPlay[:WINDow]:TOPO:DELT:PERCent?.....	124
	:DISPlay[:WINDow]:TRACe<n>:MODE.....	125
	:DISPlay[:WINDow]:TRACE<n>:MODE:MAXHOLD?	
	125
	:DISPlay[:WINDow]:TRACe:Y:DLINe.....	125
	:DISPlay[:WINDow]:TRACe:Y:DLINe:STATe	126
	:DISPlay[:WINDow]:TRACe:Y[:SCALe]:AUTO	126
	:DISPlay[:WINDow]:TRACe:Y[:SCALe]:NRLevel	126
	:DISPlay[:WINDow]:TRACe:Y[:SCALe]:NRPosition ..	127
	:DISPlay[:WINDow]:TRACe:Y[:SCALe] :PDIVision...	127
	:DISPlay[:WINDow]:TRACe:Y[:SCALe]:POSition.....	128
	:DISPlay[:WINDow]:TRACe:Y[:SCALe]:RLEVel	128
	:DISPlay[:WINDow]:TRACe:Y[:SCALe]:RLEVel:OFFSet	
	128
	:DISPlay[:WINDow]:TRACe:Y[:SCALe]:SPACing	129
	:DISPlay[:WINDow]:TRACe:Y[:SCALe]:STATe	129
	:DISPlay:SPECtrogram:DELTA:INVerse:TIME?	130
INITiate	:INITiate:CONTinuous	131
Commands	:INITiate[:IMMediate].....	131
INPut	:INPut:ATTenuation.....	132
Commands	:INPut:ATTenuation:AUTO	132

	:INPut:IMPedance.....	133
	:INPut:OFFSet.....	133
MMEMory commands	:MMEMory:CATalog?	134
	:MMEMory:CDIRectory	135
	:MMEMory:COpy	135
	:MMEMory:DELeTe	136
	:MMEMory:DESTination	136
	:MMEMory:LOAD:CORRection.....	137
	:MMEMory:LOAD:LIMit	137
	:MMEMory:LOAD:PMETer	137
	:MMEMory:LOAD:SEQuence	137
	:MMEMory:LOAD:STATe.....	138
	:MMEMory:LOAD:TRACe	138
	:MMEMory:MOVE.....	138
	:MMEMory:REName	139
	:MMEMory:STORE:CORRection	139
	:MMEMory:STORE:LIMit	139
	:MMEMory:STORE:PMETer	140
	:MMEMory:STORE:SCReen	140
	:MMEMory:STORE:SEQuence	140
	:MMEMory:STORE:STATe	140
	:MMEMory:STORE:TRACe	141
OUTPut commands	:OUTPut[:STATe]	142
SENSe commands	[:SENSe]:ACPR:ACHannel<n> :BANDwidth BWIDth	146
	[:SENSe]:ACPR:ACHannel<n>:HLIMit.....	146
	[:SENSe]:ACPR:ACHannel<n>:LLIMit.....	147
	[:SENSe]:ACPR:ACHannel<n>:OFFSet.....	147
	[:SENSe]:ACPR:BANDwidth BWIDth	147
	[:SENSe]:ACPR:HLIMit.....	148
	[:SENSe]:ACPR:LLIMit.....	148
	[:SENSe]:ACPR:HELP:STATe	148
	[:SENSe]:ACPR:SPACe.....	149
	[:SENSe]:ASET:AMPLitude	149
	[:SENSe]:ASET:AMPLitude:AUTO.....	149
	[:SENSe]:ASET:RUN	150
	[:SENSe]:ASET:SPAN.....	150

[SENSe]:ASET:SPAN:AUTO	150
[SENSe]:AVERage:COUNT.....	151
[SENSe]:AVERage:STATe.....	151
[SENSe]:AVERage:TYPE.....	151
[SENSe]:BANDwidth BWIDth[:RESolution].....	152
[SENSe]:BANDwidth BWIDth[:RESolution]:AUTO	152
[SENSe]:BANDwidth BWIDth:VIDeo	153
[SENSe]:BANDwidth BWIDth:VIDeo:AUTO.....	153
[SENSe]:CHANnel:SPACe:DOWN	153
[SENSe]:CHANnel:SPACe:UP.....	154
[SENSe]:CNR:CHANnel:SPACe	154
[SENSe]:CNR:DELTamarker:MODE	154
[SENSe]:CORRection:CSET<n>:DATA.....	155
[SENSe]:CORRection:CSET<n>:STATe	155
[SENSe]:CORRection:CSET<n>:DELeTe	156
[SENSe]:CSO:CHANnel:SPACe.....	156
[SENSe]:CTB:CHANnel:SPACe.....	156
[SENSe]:DEMod:EARPhone:TYPE.....	157
[SENSe]:DEMod:EARPhone:VOLume	157
[SENSe]:DEMod:EARPhone:GAIN	157
[SENSe]:DEMod:FILTer:LPASs	158
[SENSe]:DEMod:IFBW	158
[SENSe]:DEMod:SQUelch:LEVel.....	159
[SENSe]:DETEctor[:FUNCTion]	159
[SENSe]:DETEctor[:FUNCTion]:AUTO.....	159
[SENSe]:EMIFilter:STATe.....	160
[SENSe]:EMIFilter:BANDwidth BWIDth [:RESolution]	160
[SENSe]:FREQuency:CENTer	161
[SENSe]:FREQuency:CENTer:STEP	161
[SENSe]:FREQuency:CENTer:STEP:AUTO	161
[SENSe]:FREQuency:OFFSet.....	162
[SENSe]:FREQuency:SPAN.....	162
[SENSe]:FREQuency:SPAN:FULL.....	162
[SENSe]:FREQuency:SPAN:PREVious	162
[SENSe]:FREQuency:STARt.....	163
[SENSe]:FREQuency:STOP	163
[SENSe]:HARMonic:FUNDamental:FREQuency	163
[SENSe]:HARMonic:NUMBer.....	164
[SENSe]:LIMit<n>:DELeTe	164
[SENSe]:JITTer:OFFSet:STARt.....	164
[SENSe]:JITTer:OFFSet:STOP	164
[SENSe]:NDB:BANDwidth BWIDth.....	165

[SENSe]:OCBW:BANDwidth BWIDth	165
[SENSe]:OCBW:PERCent	165
[SENSe]:OCBW:SPACe	166
[SENSe]:P1DB:AVERAge:COUNT	166
[SENSe]:P1DB:GAIN:OFFSet	166
[SENSe]:PMETer:FREQuency	167
[SENSe]:PMETer:HLIMit	167
[SENSe]:PMETer:HOLD:STATe	167
[SENSe]:PMETer:LLIMit	168
[SENSe]:PMETer:PSEnSor:MODE	168
[SENSe]:PMETer:RECORDing:TIME	168
[SENSe]:PMETer:RECORDing:TIME:STEP	169
[SENSe]:POWer[:RF]:GAIN	169
[SENSe]:SEMask:BANDwidth BWIDth:INTegration	170
[SENSe]:SEMask:BANDwidth BWIDth [RESolution]	170
[SENSe]:SEMask:BANDwidth BWIDth [RESolution]:AUTO	170
[SENSe]:SEMask:CARRier:AUTO	171
[SENSe]:SEMask:CARRier:CPSD	171
[SENSe]:SEMask:CARRier:POWer	172
[SENSe]:SEMask:FREQuency:SPAN	172
[SENSe]:SEMask:GWLan:MODulation	172
[SENSe]:SEMask:HELP:STATe	173
[SENSe]:SEMask:NWLan:CHANnel: BANDwidth BWIDth	173
[SENSe]:SEMask:OFFSet<n>:ADDition: BANDwidth BWIDth[:RESolution]?	174
[SENSe]:SEMask:OFFSet<n>:ADDition: FREQuency:START?	176
[SENSe]:SEMask:OFFSet<n>:ADDition: FREQuency:STOP?	176
[SENSe]:SEMask:OFFSet<n>:ADDition: STARt:ABSolute?	177
[SENSe]:SEMask:OFFSet<n>:ADDition: STOP:ABSolute?	177
[SENSe]:SEMask:OFFSet<n>:BANDwidth BWIDth[:RESolution]	177
[SENSe]:SEMask:OFFSet<n>:BANDwidth BWIDth [RESolution]:AUTO	178
[SENSe]:SEMask:OFFSet<n>:FREQuency:STARt	178
[SENSe]:SEMask:OFFSet<n>:FREQuency:STOP	179
[SENSe]:SEMask:OFFSet<n>:STARt:ABSolute	179

	[SENSe]:SEMask:OFFSet<n>:STARt:RELative	179
	[SENSe]:SEMask:OFFSet<n>:STATe	180
	[SENSe]:SEMask:OFFSet<n>:STOP:ABSolute	180
	[SENSe]:SEMask:OFFSet<n>:STOP:ABSolute	
	:COUPle.....	181
	[SENSe]:SEMask:OFFSet<n>:STOP:RELative.....	181
	[SENSe]:SEMask:OFFSet<n>:STOP:RELative	
	:COUPle.....	182
	[SENSe]:SEMask:OFFSet<n>:TEST	182
	[SENSe]:SEMask:SELEct.....	182
	[SENSe]:SEMask:TYPE	183
	[SENSe]:SEMask:W3GPP:DUPLex:TYPE.....	183
	[SENSe]:SEMask:W3GPP:FDD:ADDition:LIMit.....	184
	[SENSe]:SEMask:W3GPP:FDD:ADDition	
	:MOPower	184
	[SENSe]:SEMask:W3GPP:FDD:MOPower.....	184
	[SENSe]:SEMask:W3GPP:FDD:TRANsmit:MODE..	185
	[SENSe]:SEMask:W3GPP:TDD:CHIP:RATE.....	185
	[SENSe]:SEMask:W3GPP:TDD:MOPower	186
	[SENSe]:SEMask:W3GPP:TDD:TRANsmit:MODE..	186
	[SENSe]:SEMask:WIMax:CHANnel:	
	BANDwidth BWIDth	187
	[SENSe]:SEQuence<n>:DELEte.....	187
	[SENSe]:SWEep:EGATe:DELAy.....	187
	[SENSe]:SWEep:EGATe:LENGth	188
	[SENSe]:SWEep:EGATe:STATe.....	188
	[SENSe]:SWEep:MODE.....	188
	[SENSe]:SWEep:TIME	189
	[SENSe]:SWEep:TIME:AUTO	189
	[SENSe]:TOI:REFerence	189
	[SENSe]:TOI:LIMit.....	190
SOURCE commands	:SOURce:POWEr[:LEVel][:IMMediate][:AMPLitude] ..	191
	:SOURce:POWEr[:LEVel][:IMMediate][:AMPLitude]	
	:OFFSet.....	191
	:SOURce:POWEr[:LEVel][:IMMediate][:AMPLitude]	
	:STEP	192
	:SOURce:POWEr[:LEVel][:IMMediate][:AMPLitude]:	
	STEP:AUTO	192
	:SOURce:POWEr:MODE	193
	:SOURce:POWEr:SWEep.....	193

SYSTem	:SYSTem:ALARm:STATe.....	194
commands	:SYSTem:CLOCK<n>:DATE.....	195
	:SYSTem:CLOCK<n>:MODE	195
	:SYSTem:CLOCK<n>:STATe	196
	:SYSTem:CLOCK<n>:TIME	196
	:SYSTem:COMMunicate:GPIB[:SELF]:ADDReSS	196
	:SYSTem:COMMunicate:LANReset	197
	:SYSTem:COMMunicate:SERial[:RECeive]:BAUD.....	197
	:SYSTem:COMMunicate:USB:MODE	197
	:SYSTem:DATE	197
	:SYSTem:ERRor:CLEAr	198
	:SYSTem:ERRor[:NEXT]?.....	198
	:SYSTem:KLOCK.....	198
	:SYSTem:PRESet.....	198
	:SYSTem:PRESet:TYPE	199
	:SYSTem:PRESet:USER:SAVE	199
	:SYSTem:REBoot.....	199
	:SYSTem:SHUTdown	199
	:SYSTem:TIME	199
	:SYSTem:UPDate	200
	:SYSTem:VERSion:HARDware?	200
	:SYSTem:VERSion:SOFTware?	200
STATus	:STATus:OPERation:CONDition?.....	202
commands	:STATus:OPERation:ENABle	203
	:STATus:OPERation[:EVENT]?.....	203
	:STATus:OPERation:NTRansition.....	204
	:STATus:OPERation:PTRansition.....	204
	:STATus:QUEStionable:CONDition?	205
	:STATus:QUEStionable:ENABle	205
	:STATus:QUEStionable[:EVENT]?.....	206
	:STATus:QUEStionable:NTRansition.....	206
	:STATus:QUEStionable:PTRansition.....	207
	:STATus:QUEStionable:FREQuency:CONDition?.....	207
	:STATus:QUEStionable:FREQuency:ENABle	208
	:STATus:QUEStionable:FREQuency[:EVENT]?.....	208
	:STATus:QUEStionable:FREQuency:NTRansition.....	208
	:STATus:QUEStionable:FREQuency:PTRansition.....	209
	:STATus:QUEStionable:ACPLimit:CONDition?.....	209
	:STATus:QUEStionable:ACPLimit:ENABle	210
	:STATus:QUEStionable:ACPLimit[:EVENT]?.....	210

	:STATus:QUESTionable:ACPLimit:NTRansition.....	211
	:STATus:QUESTionable:ACPLimit:PTRansition.....	211
	:STATus:QUESTionable:SEMLimit:CONDition?	212
	:STATus:QUESTionable:SEMLimit:ENABLE?	213
	:STATus:QUESTionable:SEMLimit[:EVENT]?	213
	:STATus:QUESTionable:SEMLimit:NTRansition	214
	:STATus:QUESTionable:SEMLimit:PTRansition	215
	:STATus:QUESTionable:TOILimit:CONDition?	215
	:STATus:QUESTionable:TOILimit:ENABLE.....	216
	:STATus:QUESTionable:TOILimit[:EVENT]?	216
	:STATus:QUESTionable:TOILimit:NTRansition	216
	:STATus:QUESTionable:TOILimit:PTRansition	217
	:STATus:PRESet.....	217
TRACe	:TRACe[:DATA]?	217
commands	:PIXel? TRACe<n>	218
TRIGger	:TRIGger[:SEQUence]:DELay	220
commands	:TRIGger[:SEQUence]:DEMod:DELay	220
	:TRIGger[:SEQUence]:DEMod:LEVel	221
	:TRIGger[:SEQUence]:DEMod:MODE	221
	:TRIGger[:SEQUence]:DEMod:SLOPe	221
	:TRIGger[:SEQUence]:DEMod:SOURce	222
	:TRIGger[:SEQUence]:DEMod:TIME:STARt.....	222
	:TRIGger[:SEQUence]:DEMod:TIME:STOP.....	222
	:TRIGger[:SEQUence]:EXTernal:SLOPe.....	223
	:TRIGger[:SEQUence]:MODE	223
	:TRIGger[:SEQUence]:PMETer:SOURce	223
	:TRIGger[:SEQUence]:SOURce	224
	:TRIGger[:SEQUence]:VIDeo:FREQuency	224
	:TRIGger[:SEQUence]:VIDeo:LEVel.....	224
	:TRIGger[:SEQUence]:VIDeo:SLOPe.....	225
UNIT commands	:UNIT:PMETer:POWEr.....	226
	:UNIT:POWEr	226

SCPI Commands

*CLS	74
*IDN?	74
*ESE	75
*ESR?	75
*OPC	75
*RST	76
*SRE	76
*STB?	76
*TST?	76
*WAI	77

*CLS

Set →

Description	<p>The *CLS command clears the Standard Event Status, Operation Status and Questionable Status registers. The corresponding Enable registers in each of the above registers are not cleared.</p> <p>If a <NL> newline code immediately precedes a *CLS command, the Error Que and the MAV bit in the Status Byte Register is also cleared.</p>
Syntax	*CLS

*IDN?

→ Query

Description	<p>Queries the manufacturer, model number, serial number, and firmware version of the instrument.</p>
Query Syntax	*IDN?

Return parameter	<string>	Returns the instrument identification as a string in the following format: GWINSTEK,GSP-9300,XXXXXXXX,T.X.X.X.X Manufacturer: GWINSTEK Model number : GSP-9300 Serial number : XXXXXXXX Firmware version : T.X.X.X.X
------------------	----------	---

*ESE

Set →

→ Query

Description	Sets or queries the Standard Event Status Enable register.	
Syntax	*ESE <NR1>	
Query Syntax	*ESE?	
Parameter	<NR1>	0~255
Return parameter	<NR1>	Returns the bit sum of the Standard Event Status Enable register.

*ESR?

→ Query

Description	Queries the Standard Event Status register. The Event Status register is cleared after it is read.	
Query Syntax	*ESR?	
Return parameter	<NR1>	Returns the bit sum of the Standard Event Status register and clears the register.

*OPC

Set →

→ Query

Description	<p>The *OPC command sets the OPC bit (bit0) of the Standard Event Status Register when all current commands have been processed.</p> <p>The *OPC? Query returns 1 when all the outstanding commands have completed.</p>	
-------------	---	--

Syntax	*OPC
Query Syntax	*OPC?
Return parameter	1 Returns 1 when all the outstanding commands have completed.

*RST

Description	*RST will perform a factory reset.
Syntax	*RST

*SRE

Description	Sets or queries the Service Request Enable register. The Service Request Enable register determines which registers of the Status Byte register are able to generate service requests.
Syntax	*SRE <NR1>
Query Syntax	*SRE?
Parameter	<NR1> 0~255
Return parameter	<NR1> Returns the bit sum of the Service Request Enable register.

*STB?

Description	Queries the bit sum of the Status Byte register with MSS (Master summary Status).
Query Syntax	*STB?
Return parameter	<NR1> Returns the bit sum of the Status Byte register with the MSS bit (bit 6).

*TST?

Description	Returns the result of a self-test. The GSP-9300 does not support performing a selftest and thus will always return "0" for this query.
-------------	--

Query Syntax *TST?

Return parameter 0 Returns "0"

*WAI

Set →

Description Prevents any other commands or queries from being executed until all outstanding commands have completed.

Syntax *WAI

CALCulate Commands

:CALCulate:ACPR:ACHannel<n>:HLIMit:FAIL?	79
:CALCulate:ACPR:ACHannel<n>:LLIMit:FAIL?	80
:CALCulate:ACPR:ACHannel<n>:LOWer?	80
:CALCulate:ACPR:ACHannel<n>:UPPer?	80
:CALCulate:ACPR:ACHannel<n>:STATe	81
:CALCulate:ACPR:CHANnel:HLIMit:FAIL?	81
:CALCulate:ACPR:CHANnel:LLIMit:FAIL?	82
:CALCulate:ACPR:CHPower?	82
:CALCulate:ACPR:STATe	82
:CALCulate:BFSK:STATe	83
:CALCulate:BFSK:REStart	83
:CALCulate:BFSK:RESult?	83
:CALCulate:CNR:RESult?	84
:CALCulate:CNR:STATe	84
:CALCulate:CSO:RESult?	84
:CALCulate:CSO:STATe	85
:CALCulate:CTB:RESult?	85
:CALCulate:CTB:STATe	85
:CALCulate:CTB:REStart	86
:CALCulate:DELTamarker<n>:PAIR:SPAN	86
:CALCulate:DELTamarker<n>:PAIR:CENTer	86
:CALCulate:DELTamarker<n>:X	86
:CALCulate:DELTamarker<n>:Y?	87
:CALCulate:DEMod:AM:RESult:CURREnt?	87
:CALCulate:DEMod:AM:RESult:MINimum?	88
:CALCulate:DEMod:AM:RESult:MAXimum?	88
:CALCulate:DEMod:AM:STATe	88
:CALCulate:DEMod:EARPhone:STATe	89

:CALCulate:DEMod:FM:RESult:CURRent?	89
:CALCulate:DEMod:FM:RESult:MINimum?	90
:CALCulate:DEMod:FM:RESult:MAXimum?	90
:CALCulate:DEMod:FM:STATe	91
:CALCulate:DEMod:RESet	91
:CALCulate:HARMonic:DISToRtion?	91
:CALCulate:HARMonic:RESult?	92
:CALCulate:HARMonic:STATe	92
:CALCulate:JITTer:STATe	92
:CALCulate:JITTer:CARRier:POWer?	93
:CALCulate:JITTer:PHASe?	93
:CALCulate:JITTer:TIME?	93
:CALCulate:LIMit<n>:CLEar	94
:CALCulate:LIMit<n>:DATA	94
:CALCulate:LIMit:FAIL?	94
:CALCulate:LIMit:LOW	95
:CALCulate:LIMit:HIGH	95
:CALCulate:LIMit<n>:MARKer	95
:CALCulate:LIMit:MODE	96
:CALCulate:LIMit:STATe	96
:CALCulate:LIMit<n>:TRACe	96
:CALCulate:LIMit:TYPE	97
:CALCulate:MARKer:AOff	97
:CALCulate:MARKer<n>:FCOunt:RESolution	97
:CALCulate:MARKer<n>:FCOunt:RESolution	
:AUTO	98
:CALCulate:MARKer<n>:FCOunt:STATe	98
:CALCulate:MARKer<n>:FCOunt:X?	99
:CALCulate:MARKer<n>:NOISe:STATe	99
:CALCulate:MARKer<n>:NOISe:Y?	100
:CALCulate:MARKer<n>:PEAK	100
:CALCulate:MARKer:PEAK:CTRack:STATe	100
:CALCulate:MARKer:PEAK:DATA?	101
:CALCulate:MARKer:PEAK:EXCursion	101
:CALCulate:MARKer:PEAK:SORT:TYPE	102
:CALCulate:MARKer:PEAK:TABLE:STATe	102
:CALCulate:MARKer:PEAK:THReshold	102
:CALCulate:MARKer:PEAK:THReshold:STATe	103
:CALCulate:MARKer<n>:SET	103
:CALCulate:MARKer<n>:STATe	104
:CALCulate:MARKer:TABLE:STATe	104
:CALCulate:MARKer<n>:TRACe	104
:CALCulate:MARKer<n>:TRACe:AUTO	105

:CALCulate:MARKer<n>:TYPE 105

:CALCulate:MARKer<n>:X 106

:CALCulate:MARKer<n>:Y? 106

:CALCulate:MATH:PDIF 106

:CALCulate:MATH:LDIF 107

:CALCulate:MATH:LOFF 107

:CALCulate:NDB:STATe 107

:CALCulate:NDB:BANDwidth | BWIDth? 108

:CALCulate:NORMAlize:STATe 108

:CALCulate:OCBW:STATe 109

:CALCulate:OCBW:BANDwidth | BWIDth? 109

:CALCulate:OCBW:CHPower? 109

:CALCulate:OCBW:PSD? 110

:CALCulate:P1DB:STATe 110

:CALCulate:P1DB:GAIN:AVERAge? 111

:CALCulate:P1DB:GAIN:RESult? 111

:CALCulate:P1DB:RESult? 111

:CALCulate:PMETer:POWer? 112

:CALCulate:PMETer:LIMit:STATe 112

:CALCulate:PMETer:LIMit:FAIL? 112

:CALCulate:SEM:STATe 113

:CALCulate:SEM:OFFSet<n>:RESult? 113

:CALCulate:TOI:DIFFerential? 114

:CALCulate:TOI:FREQuency:DIFFerential? 114

:CALCulate:TOI:LIMit:STATe 114

:CALCulate:TOI:RESult? 115

:CALCulate:TOI:STATe 115

:CALCulate:ACPR:ACHannel<n>:HLIMit:
FAIL?

→ Query

Description	Returns the ACPR upper limit pass/fail judgment for the selected adjacent channel.	
Query Syntax	:CALCulate:ACPR:ACHannel<n>:HLIMit:FAIL?	
Parameter	<n>	<NR1>adjacent channel 1~3
Return parameter	0	<boolean>Pass
	1	<boolean>Fail

Query Example :CALC:ACPR:ACH1:LLIM:FAIL?
>0

:CALCulate:ACPR:ACHannel<n>:LLIMit:
FAIL?

→ Query

Description Returns the ACPR lower limit pass/fail judgment for the selected adjacent channel.

Query Syntax :CALCulate:ACPR:ACHannel<n>:LLIMit:FAIL?

Parameter <n> <NR1>adjacent channel 1~3

Return parameter 0 <boolean>Pass
1 <boolean>Fail

Query Example :CALC:ACPR:ACH1:LLIM:FAIL?
>0

:CALCulate:ACPR:ACHannel<n>:LOWer?

→ Query

Description Returns the ACPR (adjacent channel power ratio in dB) calculated for the selected lower adjacent channel.

Query Syntax :CALCulate:ACPR:ACHannel<n>:LOWer?

Parameter <n> <NR1>adjacent channel 1~3

Return parameter <NR3> Power ratio in dB

Query Example :CALC:ACPR:ACH1:LOW?
>1.801e+01

:CALCulate:ACPR:ACHannel<n>:UPPer?

→ Query

Description Returns the ACPR (adjacent channel power ratio in dB) calculated for the selected higher adjacent channel.

Query Syntax :CALCulate:ACPR:ACHannel<n>:UPPer?

Parameter	<n>	<NR1>adjacent channel 1~3
Return parameter	<NR3>	Power ratio in dB
Query Example	:CALC:ACPR:ACH1:UPP? >1.921e+01	

:CALCulate:ACPR:ACHannel<n>:STATe Set →
→ Query

Description	Sets or queries the state of the selected adjacent channel.	
Syntax	:CALCulate:ACPR:ACHannel<n>:STATe {OFF ON 0 1}	
Query Syntax	:CALCulate:ACPR:ACHannel<n>:STATe?	
Parameter	<n> 0 1 OFF ON	<NR1>adjacent channel 1~3 Disable the selected channel. Enable the selected channel. Disable the selected channel. Enable the selected channel.
Return parameter	0 1	The selected channel is disabled. The selected channel is enabled.
Query Example	:CALC:ACPR:ACH1:STAT? >1	

:CALCulate:ACPR:CHANnel:HLIMit:FAIL? → Query

Description	Returns the ACPR upper limit pass/fail judgment for the main channel. A pass indicates that every trace point in the main channel is lower than or equal to the upper limit.	
Query Syntax	:CALCulate:ACPR:CHANnel:HLIMit:FAIL?	
Return parameter	0 1	<boolean>Pass <boolean>Fail
Query Example	:CALC:ACPR:CHAN:HLIM:FAIL? >0	

:CALCulate:ACPR:CHANnel:LLIMit:FAIL? → **Query**

Description	Returns the ACPR lower limit pass/fail judgment for the main channel. A pass indicates that every trace point in the main channel is higher than or equal to the lower limit.
-------------	---

Query Syntax	:CALCulate:ACPR:CHANnel:LLIMit:FAIL?
--------------	--------------------------------------

Return parameter	0	<boolean>Pass
	1	<boolean>Fail

Query Example	:CALC:ACPR:CHAN:LLIM:FAIL? >0
---------------	----------------------------------

:CALCulate:ACPR:CHPower? → **Query**

Description	Returns the ACPR main channel power in the current chosen unit.
-------------	---

Query Syntax	:CALCulate:ACPR:CHPower?
--------------	--------------------------

Return parameter	<NR3>	Power
------------------	-------	-------

Query Example	:CALC:ACPR:CHP? >-1.028e+02
---------------	--------------------------------

:CALCulate:ACPR:STATe
Set →
 → Query

Description	Sets or queries the state of the ACPR measurement function.
-------------	---

Syntax	:CALCulate:ACPR:STATe {OFF ON 0 1}
--------	------------------------------------

Query Syntax	:CALCulate:ACPR:STATe?
--------------	------------------------

Parameter	0	ACPR is disabled.
	1	ACPR is enabled.
	OFF	ACPR is disabled.
	ON	ACPR is enabled.

Return parameter	0	ACPR is disabled.
	1	ACPR is enabled.

Query Example :CALC:ACPR:STAT?
>1

:CALCulate:BFSK:STATe

Set →

→ Query

Description Sets or queries the state of the BFSK measurement function.

Syntax :CALCulate:BFSK:STATe {OFF|ON}

Query Syntax :CALCulate:BFSK:STATe?

Parameter	OFF	BFSK is disabled.
	ON	BFSK is enabled.

Return parameter	0	BFSK is disabled.
	1	BFSK is enabled.

Query Example :CALC:BFSK:STAT?
>1

:CALCulate:BFSK:REStart

Set →

Description Restarts the BFSK measurement.

Syntax :CALC:BFSK:REST

:CALCulate:BFSK:RESult?

→ Query

Description Returns the BFSK measurement result.

Query Syntax :CALCulate:BFSK:RESult?

Return parameter	<freq deviation>,<carrier offset>	
	<freq deviation>	Frequency deviation in NRf format
	<carrier offset>	Carrier offset in NRf format

Query Example :CALC:BFSK:RES?
>4.416666667e+04,4.416666667e+04

:CALCulate:CNR:RESult?

→ Query

Description Returns the CNR measurement result in dB.

Query Syntax :CALCulate:CNR:RESult?

Return parameter <NR3> CNR measurement in dB

Query Example :CALC:CNR:RES?
>-4.959e+01

:CALCulate:CNR:STATe

Set →

→ Query

Description Sets or queries the state of the CNR measurement function.

Syntax :CALCulate:CNR:STATe {ON|OFF|1|0}

Query Syntax :CALCulate:CNR:STATe?

Parameter	0	CNR is off.
	1	CNR is on.
	OFF	CNR is off.
	ON	CNR is on.

Return parameter	0	CNR is off.
	1	CNR is on.

Query Example :CALC:CNR:STAT?
>1

:CALCulate:CSO:RESult?

→ Query

Description Returns the CSO measurement result in dB.

Query Syntax :CALCulate:CSO:RESult?

Return parameter <NR3> CSO measurement in dB

Query Example :CALC:CSO:RES?
>4.04e+00

 →
 → 

:CALCulate:CSO:STATe

Description	Sets or queries the state of the CSO measurement function.	
Syntax	:CALCulate:CSO:STATe {ON OFF 1 0}	
Query Syntax	:CALCulate:CSO:STATe?	
Parameter	0	CSO is off.
	1	CSO is on.
	OFF	CSO is off.
	ON	CSO is on.
Return parameter	0	CSO is off.
	1	CSO is on.
Query Example	:CALC:CSO:STAT? >1	

→ 

:CALCulate:CTB:RESult?

Description	Returns the CTB measurement result in dB.	
Query Syntax	:CALCulate:CTB:RESult?	
Return parameter	<NR3>	CTB measurement in dB
Query Example	:CALC:CTB:RES? >-4.237e+01	

 →
 → 

:CALCulate:CTB:STATe

Description	Sets or queries the state of the CTB measurement function.	
Syntax	:CALCulate:CTB:STATe {ON OFF 1 0}	
Query Syntax	:CALCulate:CTB:STATe?	
Parameter	0	CTB is off.
	1	CTB is on.
	OFF	CTB is off.

	ON	CTB is on.
Return parameter	0	CTB is off.
	1	CTB is on.
Query Example	:CALC:CTB:STAT? >0	

:CALCulate:CTB:REStart (Set) →

Description	Restarts the CTB measurement.
Syntax	:CALCulate:CTB:REStart

:CALCulate:DELTamarker<n>:PAIR:SPAN (Set) →

Description	Sets the span between the chosen marker and the delta marker.	
Syntax	:CALCulate:DELTamarker<n>:PAIR:SPAN <freq>	
Parameter	<n>	Marker number.
	<freq>	<NRf> frequency of span.
Example	:CALC:DELT1:PAIR:SPAN 1e+9	

:CALCulate:DELTamarker<n>:PAIR:CENTer (Set) →

Description	Takes the current span between the chosen markers and relocates that center frequency to the chosen center frequency.	
Syntax	:CALCulate:DELTamarker<n>:PAIR:CENTer <freq>	
Parameter	<n>	Marker number.
	<freq>	<NRf> center frequency.
Example	:CALC:DELT1:PAIR:CENT 1e+9	

:CALCulate:DELTamarker<n>:X (Set) →
→ (Query)

Description	Sets or queries the selected delta marker position.
-------------	---

Syntax	:CALCulate:DELTamarker<n>:X <freq>	
Query Syntax	:CALCulate:DELTamarker<n>:X?	
Parameter	<n>	Marker number.
Return parameter	<freq>	<NR3> frequency in Hz.
Example	:CALC:DELT1:X? >1e+9	

:CALCulate:DELTamarker<n>:Y?

Description	Returns the selected delta marker Y axis value.	
Query Syntax	:CALCulate:DELTamarker<n>:Y?	
Parameter	<n>	Marker number.
Return parameter	<rel_amp>	<NR3> in dB.
Example	:CALC:DELT1:Y? >-1.032e+1	

:CALCulate:DEMod:AM:RESult:CURRent?


Description	Returns the current measurement results for AM demodulation as a comma separated string.	
Query Syntax	:CALCulate:DEMod:AM:RESult:CURRent?	
Return parameter	<depth,rate,power,offset,sinad>	
	depth	Modulation depth in %.
	rate	Modulation rate in Hz.
	power	Carrier power in the current Y-axis units.
	offset	Carrier frequency offset in Hz.
	sinad	Signal to noise and distortion ratio in dB
Query Example	:CALC:DEM:AM:RES:CURR? >9.840e+1,1.02e+2,-1.12e+1,3.21e+1,1.61e+1	

:CALCulate:DEMod:AM:RESult:MINimum? → 

Description	Returns the minimum recorded measurement results for AM demodulation as a comma separated string.	
Query Syntax	:CALCulate:DEMod:AM:RESult:MINimum?	
Return parameter	<depth,rate,power,offset,sinad>	
	depth	Modulation depth in %.
	rate	Modulation rate in Hz.
	power	Carrier power in the current Y-axis units.
	offset	Carrier frequency offset in Hz.
	sinad	Signal to noise and distortion ratio in dB
Query Example	:CALC:DEM:AM:RES:MIN? >9.840e+1,1.02e+2,-1.12e+1,3.21e+1,1.61e+1	

:CALCulate:DEMod:AM:RESult:MAXimum? → 

Description	Returns the maximum recorded measurement results for AM demodulation as a comma separated string.	
Query Syntax	:CALCulate:DEMod:AM:RESult:MAXimum?	
Return parameter	<depth,rate,power,offset,sinad>	
	depth	Modulation depth in %.
	rate	Modulation rate in Hz.
	power	Carrier power in the current Y-axis units.
	offset	Carrier frequency offset in Hz.
	sinad	Signal to noise and distortion ratio in dB.
Query Example	:CALC:DEM:AM:RES:MAX? >9.840e+1,1.02e+2,-1.12e+1,3.21e+1,1.61e+1	

 **Set** →

:CALCulate:DEMod:AM:STATe → 

Description	Sets or queries the state of the AM Analysis function.
-------------	--

Syntax	:CALCulate:DEMod:AM:STATe {ON OFF 1 0}	
Query Syntax	:CALCulate:DEMod:AM:STATe?	
Parameter	0	Turn AM Analysis off.
	1	Turn AM Analysis on.
	OFF	Turn AM Analysis off.
	ON	Turn AM Analysis on.
Return parameter	0	AM Analysis is off.
	1	AM Analysis is on.
Example	:CALC:DEM:AM:STAT 1	

:CALCulate:DEMod:EARPhone:STATe  

Description	Sets or queries the state of the ear phone out port.	
Syntax	:CALCulate:DEMod:EARPhone:STATe {ON OFF 1 0}	
Query Syntax	:CALCulate:DEMod:EARPhone:STATe?	
Parameter	0	Turn the phone output off.
	1	Turn the phone output on.
	OFF	Turn the phone output off.
	ON	Turn the phone output on.
Return parameter	0	Phone output is off.
	1	Phone output is on.
Example	:CALC:DEM:EARP:STAT 1	

:CALCulate:DEMod:FM:RESult:CURRent? 

Description	Returns the current measurement results for FM demodulation as a comma separated string.	
Query Syntax	:CALCulate:DEMod:FM:RESult:CURRent?	
Return parameter	<deviation,rate,power,offset,sinad>	
	deviation	Frequency deviation in Hz.
	rate	Modulation rate in Hz.
	power	Carrier power in the current Y-axis units.
	offset	Carrier frequency offset in Hz.

	sinad	Signal to noise and distortion ratio in dB.
Query Example	:CALC:DEM:FM:RES:CURRE? >9.840e+1,1.02e+2,-1.12e+1,3.21e+1,1.61e+1	

:CALCulate:DEMod:FM:RESult:MINimum? →

Description	Returns the minimum recorded measurement results for FM demodulation as a comma separated string.	
Query Syntax	:CALCulate:DEMod:FM:RESult:MINimum?	
Return parameter	<deviation,rate,power,offset,sinad>	
	deviation	Frequency deviation in Hz.
	rate	Modulation rate in Hz.
	power	Carrier power in the current Y-axis units.
	offset	Carrier frequency offset in Hz.
	sinad	Signal to noise and distortion ratio in dB.
Query Example	:CALC:DEM:FM:RES:MIN? >9.840e+1,1.02e+2,-1.12e+1,3.21e+1,1.61e+1	

:CALCulate:DEMod:FM:RESult:MAXimum? →

Description	Returns the maximum recorded measurement results for FM demodulation as a comma separated string.	
Query Syntax	:CALCulate:DEMod:FM:RESult:MAXimum?	
Return parameter	<deviation,rate,power,offset,sinad>	
	deviation	Frequency deviation in Hz.
	rate	Modulation rate in Hz.
	power	Carrier power in the current Y-axis units.
	offset	Carrier frequency offset in Hz.
	sinad	Signal to noise and distortion ratio in dB.
Query Example	:CALC:DEM:FM:RES:MAX? >9.840e+1,1.02e+2,-1.12e+1,3.21e+1,1.61e+1	

:CALCulate:DEMod:FM:STATe

Set

→

→

Query

Description	Sets or queries the state of the FM Analysis function.	
Syntax	:CALCulate:DEMod:FM:STATe {ON OFF 1 0}	
Query Syntax	:CALCulate:DEMod:FM:STATe?	
Parameter	0	Turn FM Analysis off.
	1	Turn FM Analysis on.
	OFF	Turn FM Analysis off.
	ON	Turn FM Analysis on.
Return parameter	0	FM Analysis is off.
	1	FM Analysis is on.
Example	:CALC:DEM:FM:STAT 1	

:CALCulate:DEMod:RESet

Set

→

Description	This command will reset the max and min records for the current demodulation analysis.
Syntax	:CALCulate:DEMod:RESet

:CALCulate:HARMonic:DISTortion?

→

Query

Description	Returns the harmonic distortion as a percentage of the fundamental and as dBc.	
Query Syntax	CALCulate:HARMonic:DISTortion?	
Return parameter	<%>,<dBc>	
	<%>	THD as %. <NR1> format
	<dBc>	THD as dBc. <NRf> format
Query Example	CALC:HARM:DIST? >32.34,-9.81e+00	

:CALCulate:HARMonic:RESult?

→ **Query**

Description Returns the amplitude of each harmonic in dBm.

Query Syntax :CALCulate:HARMonic:RESult?

<fundamental>,<harmonic#2>,...<harmonic#n>

<fundamental> Returns the amplitude of the fundamental harmonic frequency in dBm.

<harmonic#n> Returns the amplitude of the nth harmonic in dBm.

Query Example :CALC:HARM:RES?

>-7.572e+01,0.00e+00,0.00e+00,0.00e+00,0.00e+00

Set →

:CALCulate:HARMonic:STATe

→ **Query**

Description Sets or queries the state of the Harmonics function.

Syntax :CALCulate:HARMonic:STATe {ON|OFF}

Query Syntax :CALCulate:HARMonic:STATe?

Parameter	OFF	Turn Harmonic measurement off.
	ON	Turn Harmonic measurement on.

Return parameter	0	Harmonic measurement is off.
	1	Harmonic measurement is on.

Example :CALC:HARM:STAT ON

Set →

:CALCulate:JITTer:STATe

→ **Query**

Description Sets or queries the state of the Jitter Analysis function.

Syntax :CALCulate:JITTer:STATe {ON|OFF|1|0}

Query Syntax :CALCulate:JITTer:STATe?

Parameter	0	Turn Jitter Analysis off.
	1	Turn Jitter Analysis on.
	OFF	Turn Jitter Analysis off.
	ON	Turn Jitter Analysis on.
Return parameter	0	Jitter Analysis is off.
	1	Jitter Analysis is on.
Example	:CALCulate:JITTer:STATe 1	

:CALCulate:JITTer:CARRier:POWer?

→ Query

Description	Returns the carrier power in the current Y-axis units.	
Query Syntax	:CALCulate:JITTer:CARRier:POWer?	
Return parameter	<NR3>	In the current Y-axis units.
Query Example	:CALC:JITT:CARR:POW? >-5.237e+01	

:CALCulate:JITTer:PHASe?

→ Query

Description	Returns the carrier phase jitter in radians.	
Query Syntax	:CALCulate:JITTer:PHASe?	
Return parameter	<NR3>	Rad
Query Example	:CALC:JITT:PHAS? >1.5307e+01	

:CALCulate:JITTer:TIME?

→ Query

Description	Returns the carrier jitter time in seconds.	
Query Syntax	:CALCulate:JITTer:TIME?	
Return parameter	<NR3>	Seconds
Query Example	:CALC:JITT:TIME? >.5.31e-08	

:CALCulate:LIMit<n>:CLEar

Set →

Description	Clears the High Limit, Low Limit and the Pass/Fail state for the selected limit line.	
Syntax	:CALCulate:LIMit<n>:CLEar	
Parameter	<n>	Selected limit line
Example	:CALC:LIM1:CLE	

:CALCulate:LIMit<n>:DATA

Set →

→ Query

Description	Sets or queries the frequency, amplitude limit of every point in the selected limit line. The data is stored in CSV format. There are total of 10 pairs of data points (20 data entries in total) for the <csv data> data.	
Syntax	:CALCulate:LIMit<n>:DATA <csv data>	
Query Syntax	:CALCulate:LIMit<n>:DATA?	
Parameter/ Return parameter	<csv data> <n>	pt#1 freq, pt#1 limit,pt#10 freq, pt#10 limit. Selected limit line
Example	:CALCulate:LIMit3:DATA? >1e+6,-10,2e+6,-30,3e+6,-40,4e+6.....	

:CALCulate:LIMit:FAIL?

→ Query

Description	Returns the Pass/Fail judgment.	
Query Syntax	:CALCulate:LIMit:FAIL?	
Return parameter	0 1	Pass Fail
Query Example	:CALC:LIM:FAIL? >1	

:CALCulate:LIMit:LOW



Description	Selects which limit line is used for the low limit.	
Syntax	:CALCulate:LIMit:LOW <limit num>	
Parameter	<limit num>	<NR1> 1~5
Example	:CALC:LIM:LOW 2	

:CALCulate:LIMit:HIGh





Description	Selects which limit line is used for the high limit.	
Syntax	:CALCulate:LIMit:HIGh <limit num>	
Parameter	<limit num>	<NR1> 1~5
Example	:CALC:LIM:HIGh 2	

:CALCulate:LIMit<n>:MARKer





Description	Sets the current marker position to a point on a limit line. The vertical position of the point is the marker's vertical position + a user-defined offset.	
Syntax	:CALCulate:LIMit<n>:MARKer <point>,<offset>	
Parameter	<point> <offset> <n>	<NR1> point 1~10 <NR3> dB Selected limit line
Example	:CALC:LIM1:MARK 5, 20	

:CALCulate:LIMit:MODE

Description	Sets or queries the Pass/Fail mode for limit line testing.	
Syntax	:CALCulate:LIMit:MODE {SING CONT}	
Query Syntax	:CALCulate:LIMit:MODE?	
Parameter	SING CONT	Stops triggering after a pass/fail result. Continues triggering after a pass/fail result.
Return Parameter	SINGLE CONTINUE	Stops triggering after a pass/fail result. Continues triggering after a pass/fail result.
Example	:CALC:LIM:MODE CONT	

:CALCulate:LIMit:STATe

Description	Turns the limit line Pass/Fail test on/off.	
Syntax	:CALCulate:LIMit:STATe {ON OFF 1 0}	
Query Syntax	:CALCulate:LIMit:STATe?	
Parameter	0 1 OFF ON	Pass/Fail test is off. Pass/Fail test is on. Pass/Fail test is off. Pass/Fail test is on.
Return parameter	0 1	Pass/Fail test is off. Pass/Fail test is on.
Example	:CALC:LIM:STAT 1	

:CALCulate:LIMit<n>:TRACe



Description	Creates a limit line from the currently selected trace with a user defined offset.
Syntax	:CALCulate:LIMit<n>:TRACe <offset>

Parameter	<n> <offset>	<NR1> limit line 1~5 <NR3> in dB
-----------	-----------------	-------------------------------------

Example :CALC:LIM2:TRAC 10

:CALCulate:LIMit:TYPE

Set →

→ Query

Description Sets or queries the Pass/Fail conditions for the limit line testing.

Syntax :CALCulate:LIMit:TYPE {ALL|MAX|MIN}

Query Syntax :CALCulate:LIMit:TYPE?

Parameter/ Return Parameter	ALL	All-in.
	MAX	Max-In
	MIN	Min-In

Example :CALC:LIM:TYPE ALL

:CALCulate:MARKer:AOff

Set →

Description Turns all the markers off.

Syntax :CALCulate:MARKer:AOff

Example :CALC:MARK:AOff

:CALCulate:MARKer<n>:FCOut:
RESolution

Set →

→ Query

Description Sets or queries the frequency counter resolution in Hz for the selected marker.


Syntax :CALCulate:MARKer<n>:FCOut:RESolution <freq>

Query Syntax :CALCulate:MARKer<n>:FCOut:RESolution?

Parameter	<n> <freq>	<NR1>Marker number 1~6*. Frequency resolution in Hz**.
-----------	---------------	---


Return parameter	<freq>	Frequency resolution in Hz.
Note	<p>* Only one marker can be selected at a time to use the marker counter function.</p> <p>The selected marker counter will disable the previously selected marker counter.</p> <p>** Only 1000, 100, 10, 1 Hz are meaningful.</p>	
Example	<pre>:CALC:MARK1:FCO:RES? >1.0e+3</pre>	

**:CALCulate:MARKer<n>:FCOunt:
RESolution:AUTO**



Description	Sets the frequency counter resolution Auto setting on/off.	
Syntax	:CALCulate:MARKer<n>:FCOunt:RESolution:AUTO {ON OFF 1 0}	
Query Syntax	:CALCulate:MARKer<n>:FCOunt:RESolution:AUTO?	
Parameter	<n>	<NR1>Marker number 1~6
	0	Auto is off.
	1	Auto is on.
	OFF	Auto is off.
	ON	Auto is on.
Return parameter	0	Auto is off.
	1	Auto is on.
Example	:CALC:MARK1:FCO:RES:AUTO?	

:CALCulate:MARKer<n>:FCOunt:STATe



Description	Sets or queries the state of the frequency counter function.	
Syntax	:CALCulate:MARKer<n>:FCOunt:STATe {ON OFF 1 0}	
Query Syntax	:CALCulate:MARKer<n>:FCOunt:STATe?	

Parameter	<n>	<NR1>Marker number 1~6
	0	Turn frequency counter off.
	1	Turn frequency counter on.
	OFF	Turn frequency counter off.
	ON	Turn frequency counter on.
Return parameter	0	Frequency counter is off.
	1	Frequency counter is on.
Example	:CALC:MARKer1:FCO:STAT 1	

:CALCulate:MARKer<n>:FCOunt:X?

→ Query

Description	Returns the counter frequency of the selected marker in Hz.	
Query Syntax	:CALCulate:MARKer<n>:FCOunt:X?	
Parameter	<n>	<NR1> Marker number 1~6.
Return parameter	<freq>	<NR3> Frequency in Hz.
Example	:CALC:MARK1:FCO:X? >2.0083e+8	

:CALCulate:MARKer<n>:NOISe:STATe

Set →

→ Query

Description	Sets or queries the state of the Marker Noise function.	
Syntax	:CALCulate:MARKer<n>:NOISe:STATe {ON OFF 1 0}	
Query Syntax	:CALCulate:MARKer<n>:NOISe:STATe?	
Parameter	<n>	<NR1>Marker number 1~6.
	0	Turn marker noise off.
	1	Turn marker noise on.
	OFF	Turn marker noise off.
	ON	Turn marker noise on.
Return parameter	0	Marker noise is off.
	1	Marker noise is on.
Example	:CALC:MARK2:NOIS:STAT ON	

:CALCulate:MARKer<n>:NOISe:Y? Set →
→ Query

Description	Returns the normalized noise level over a BW of 1Hz from the marker position.	
Query Syntax	:CALCulate:MARKer<n>:NOISe:Y?	
Parameter	<n>	<NR1> Marker number 1~6.
Return parameter	<NR3>	Normalized noise level in the Y-axis unit.
Example	:CALC:MARK1:NOIS:Y? >1.166e+2	

:CALCulate:MARKer<n>:PEAK Set →

Description	Sets the selected marker to the selected peak.	
Query Syntax	:CALCulate:MARKer<n>:PEAK {MAXimum MINimum NEXT RIGHT LEFT}	
Parameter	<n>	<NR1> Marker number 1~6
	MAXimum	Highest peak value
	MIMimum	Lowest peak value
	NEXT	Next peak
	RIGHT	Next peak right
	LEFT	Next peak left
Example	:CALC:MARK1:PEAK NEXT	

:CALCulate:MARKer:PEAK:CTrack:STATe Set →
→ Query

Description	Sets or queries the state of the Peak Track function. The Peak Track function only applies to the currently selected marker.	
Syntax	:CALCulate:MARKer:PEAK:CTrack:STATe {ON OFF 1 0}	
Query Syntax	:CALCulate:MARKer:PEAK:CTrack:STATe?	

Parameter	0	Turn peak track off.
	1	Turn peak track on.
	OFF	Turn peak track off.
	ON	Turn peak track on.
Return parameter	0	Peak track is off.
	1	Peak track is on.
Example	:CALC:MARK:PEAK:CTR:STAT ON	

:CALCulate:MARKer:PEAK:DATA?

→ Query

Description	<p>Returns all the top 10 peak data values in CSV format (returns the contents of the peak table).</p> <p>The <csv data> data contains 10 pairs of data from the top 10 peaks. Each pair includes the peak frequency and the peak amplitude. There are a total of 10 pairs of data points (20 data entries in total) for the <csv data> data.</p>	
Query syntax	:CALCulate:MARKer:PEAK:DATA?	
Return parameter	<csv data>	pk#1 freq, pk#1 amp,..... pk#10 freq, pk#10 amp.
Example	:CALC:MARK:PEAK:DATA? >1.250e+08,-5.052e+01,1.065000000e+09,...	

Set →

:CALCulate:MARKer:PEAK:EXCursion

→ Query

Description	Sets or queries the peak excursion value.	
Syntax	:CALCulate:MARKer:PEAK:EXCursion <rel ampl>	
Query Syntax	:CALCulate:MARKer:PEAK:EXCursion?	
Parameter	<rel ampl>	Peak excursion dB (offset from threshold)
Return parameter	<NR3>	Peak excursion in dB.
Example	:CALC:MARK:PEAK:EXC 6 db	

Set →
→ Query

:CALCulate:MARKer:PEAK:SORT:TYPE

Description	Sets or queries the peak sort type for the peak table.	
Syntax	:CALCulate:MARKer:PEAK:SORT:TYPE {FREQuency AMPLitude}	
Query Syntax	:CALCulate:MARKer:PEAK:SORT:TYPE?	
Parameter/ Return parameter	FREQuency	Sort by frequency.
	AMPLitude	Sort by amplitude.
Example	:CALC:MARK:PEAK:SORT:TYPE FREQ	

Set →
→ Query

:CALCulate:MARKer:PEAK:TABLE:STATe

Description	Sets or queries the state of the Peak Table.	
Syntax	:CALCulate:MARKer:PEAK:TABLE:STATe {ON OFF 1 0}	
Query Syntax	:CALCulate:MARKer:PEAK:TABLE:STATe?	
Parameter	0	Turn peak table off.
	1	Turn peak table on.
	OFF	Turn peak table off.
	ON	Turn peak table on.
Return parameter	0	peak table is off.
	1	peak table is on.
Example	:CALC:MARK:PEAK:TABL:STAT ON	

Set →
→ Query

:CALCulate:MARKer:PEAK:THReshold

Description	Sets or queries the peak threshold value.	
Syntax	:CALCulate:MARKer:PEAK:THReshold < ampl>	
Query Syntax	:CALCulate:MARKer:PEAK:THReshold?	
Parameter	< ampl>	Peak Threshold level

Return parameter	<NR3>	Peak threshold. Note: the unit returned depends on the currently set vertical units.
------------------	-------	--

Example :CALC:MARK:PEAK:THR -3 dBm

:CALCulate:MARKer:PEAK:THReshold:
STATe

Set →
→ Query

Description Sets or queries the state of the Peak Threshold.

Syntax :CALCulate:MARKer:PEAK:THReshold:STATe
{ON|OFF|1|0}

Query Syntax :CALCulate:MARKer:PEAK:THReshold:STATe?

Parameter	0	Turn peak threshold off.
	1	Turn peak threshold on.
	OFF	Turn peak threshold off.
	ON	Turn peak threshold on.

Return parameter	0	Peak threshold is off.
	1	Peak threshold is on.

Example :CALC:MARK:PEAK:THR:STAT ON

:CALCulate:MARKer<n>:SET

Set →

Description Sets the selected marker to one of five preset positions.

Query Syntax :CALCulate:MARKer<n>:SET {CENTer|START|STOP
|STEP|RLEVel}

Parameter	<n>	<NR1> Marker number 1~6
	CENTer	Set to center frequency
	START	Set to start frequency
	STOP	Set to stop frequency
	STEP	Set to CF STEP frequency
	RLEVel	Set to the Reference level

Example :CALC:MARK1:SET CENT

:CALCulate:MARKer<n>:STATe

Set →
→ Query

Description	Sets or queries the state of the selected marker.	
Syntax	:CALCulate:MARKer<n>:STATe {ON OFF 1 0}	
Query Syntax	:CALCulate:MARKer<n>:STATe?	
Parameter	<n>	<NR1> Marker number 1~6
	0	Turn the selected marker off.
	1	Turn the selected marker on.
	OFF	Turn the selected marker off.
	ON	Turn the selected marker on.
Return parameter	0	The selected marker is off.
	1	The selected marker on.
Example	:CALC:MARK1:STAT ON	

:CALCulate:MARKer:TABLE:STATe

Set →
→ Query

Description	Sets or queries the state of the marker table.	
Syntax	:CALCulate:MARKer:TABLE:STATe {ON OFF 1 0}	
Query Syntax	:CALCulate:MARKer:TABLE:STATe	
Parameter	0	Turn the table off.
	1	Turn the table on.
	OFF	Turn the table off.
	ON	Turn the table on.
Return parameter	0	The table is off.
	1	The table is on.
Example	:CALC:MARK:TABL:STAT ON	

:CALCulate:MARKer<n>:TRACe

Set →
→ Query

Description	Assigns the selected marker to a trace. Queries which trace the selected marker is assigned to.	
Syntax	:CALCulate:MARKer<n>:TRACe <trace name>	

Query Syntax	:CALCulate:MARKer<n>:TRACe?	
Parameter/	<n>	<NR1> Marker number 1~6
Return parameter	<trace name>	The name of the trace: (1, 2, 3, 4)
Example	:CALC:MARK2:TRAC 1	

Set →
→ Query

:CALCulate:MARKer<n>:TRACe:AUTO

Description	Sets or queries the state of the Marker Trace function. Allows the selected marker to be automatically assigned to a trace (on) or be to manually assigned a trace (off).	
Syntax	:CALCulate:MARKer<n>:TRACe:AUTO {ON OFF 1 0}	
Query Syntax	:CALCulate:MARKer<n>:TRACe:AUTO?	
Parameter	<n> 0 1 OFF ON	<NR1> Marker number 1~6 Turn the auto function off. Turn the auto function on. Turn the auto function off. Turn the auto function on.
Return parameter	0 1	The auto function is off. The auto function is on.
Example	:CALC:MARK2:TRAC:AUTO OFF	

Set →
→ Query

:CALCulate:MARKer<n>:TYPE

Description	Sets or queries the marker type.	
Syntax	:CALCulate:MARKer<n>:TYPE {NORMal DELTA}	
Query Syntax	:CALCulate:MARKer<n>:TYPE?	
Parameter/	<n>	<NR1> Marker number 1~6
Return parameter	<NORMal> <DELTA>	Normal marker Delta marker
Example	:CALC:MARK1:TYPE NORM	

:CALCulate:MARKer<n>:X

Set →
→ Query

Description	Sets or returns the marker position in Hz.	
Syntax	:CALCulate:MARKer<n>:X <freq>	
Query Syntax	:CALCulate:MARKer<n>:X?	
Parameter/ Return parameter	<n> <freq>	<NR1> Marker number 1~6 Hz
Example	:CALC:MARK4:X 2.0e+6	

:CALCulate:MARKer<n>:Y?

→ Query

Description	Returns the marker's vertical position in the current unit.	
Query Syntax	:CALCulate:MARKer<n>:Y?	
Parameter	<n>	<NR1> Marker number 1~6
Return parameter	<NR3>	Power or voltage
Example	:CALC:MARK1:Y? >-5.43e+1	

:CALCulate:MATH:PDIF

Set →

Description	Calculates the power difference between two traces (T1 -the first trace operand- and T2 -the second trace operand-).	
Syntax	:CALCulate:MATH:PDIF <Destination Trace,T1,T2>	
Parameter	< Destination Trace>* < T1> < T2>	TRACe1, TRACe2, TRACe3 or TRACe4
Note	* The destination trace cannot be the same as the T1 or T2 trace.	
Example	:CALC:MATH:PDIF TRAC1,TRAC2,TRAC3	

:CALCulate:MATH:LDIF




Description	Calculates the logarithmic difference between two traces (T1 – the first trace operand and T2 – the second trace operand) and assigns the designated reference level to the destination trace.	
Syntax	:CALCulate:MATH:LDIF <Destination Trace,T1,T2, Ref>	
Parameter	<div> <div>< Destination Trace>*</div> <div>< T1></div> <div>< T2></div> <div><Ref></div> </div>	<div> <div>TRACe1, TRACe2, TRACe3 or TRACe4</div> <div><NR1>Reference level</div> </div>
Note	* The destination trace cannot be the same the T1 or T2 traces.	
Example	:CALC:MATH:LDIF TRAC1,TRAC2,TRAC3,20	


:CALCulate:MATH:LOFF



Description	Adds an offset to T1 -the source trace- and puts the result into a destination trace.	
Syntax	:CALCulate:MATH:LOFF <Destination Trace,T1,offset>	
Parameter	<div> <div>< Destination Trace >*</div> <div>< T1> -source trace-</div> <div><offset></div> </div>	<div> <div>TRACe1, TRACe2, TRACe3 or TRACe4</div> <div><NRf>Offset in dB</div> </div>
Note	* The destination trace cannot be the same as the source trace.	
Example	:CALC:MATH:LOFF TRAC1,TRAC2,6	



:CALCulate:NDB:STATe



Description	Sets or queries the state of the NdB BW function.
Syntax	:CALCulate:NDB:STATe {ON OFF 1 0}

Query Syntax	:CALCulate:NDB:STATe?	
Parameter	0	Turn NdB BW off.
	1	Turn NdB BW on.
	OFF	Turn NdB BW off.
	ON	Turn NdB BW on.
Return parameter	0	NdB BW is off.
	1	NdB BW is on.
Example	:CALC:NDB:STAT ON	

:CALCulate:NDB:BANDwidth|BWIDth?

Description	Returns the NdB bandwidth measurement.	
Query Syntax	:CALCulate:NDB:BANDwidth BWIDth?	
Return parameter	<NR3>	NdB bandwidth in Hz.
Example	:CALC:NDB:BAND? >5.5e+04	

:CALCulate:NORMalize:STATe

Description	Turns the tracking generator normalization on/off or queries its state.	
Syntax	:CALCulate:NORMalize:STATe{ON OFF 1 0}	
Query Syntax	:CALCulate:NORMalize:STATe?	
Parameter	0	Turn normalization off.
	1	Turn normalization on.
	OFF	Turn normalization off.
	ON	Turn normalization on.
Return parameter	0	normalization is off.
	1	normalization is on.
Example	:CALC:NORM:STAT ON	

:CALCulate:OCBW:STATe

Set →

→ Query

Description	Turns the OCBW measurement on/off or queries its state.	
-------------	---	--

Syntax	:CALCulate:OCBW:STATe {ON OFF 1 0}	
--------	------------------------------------	--

Query Syntax	:CALCulate:OCBW:STATe?	
--------------	------------------------	--

Parameter	0	Turn OCBW off.
	1	Turn OCBW on.
	OFF	Turn OCBW off.
	ON	Turn OCBW on.

Return parameter	0	OCBW is off.
	1	OCBW is on.

Example	:CALC:OCBW:STAT ON
---------	--------------------

:CALCulate:OCBW:BANDwidth|BWIDth?

→ Query

Description	Returns the OCBW bandwidth measurement.	
-------------	---	--

Query Syntax	:CALCulate:OCBW:BANDwidth BWIDth?	
--------------	-----------------------------------	--

Return parameter	<NR3>	OCBW bandwidth in Hz.
------------------	-------	-----------------------

Example	:CALC:OCBW:BAND?
	>4.1e+03

:CALCulate:OCBW:CHPower?

→ Query

Description	Returns the OCBW channel power measurement.	
-------------	---	--

Query Syntax	:CALCulate:OCBW:CHPower?	
--------------	--------------------------	--

Return parameter	<NR3>	OCBW channel power in the current Y-axis unit.
------------------	-------	--

Example	:CALC:OCBW:CHP?
	>9.13e+01

:CALCulate:OCBW:POWer?

→ **Query**

Description	Returns the OCBW total power measurement.	
Query Syntax	:CALCulate:OCBW:POWer?	
Return parameter	<NR3>	OCBW total power in the current Y-axis unit.
Example	:CALC:OCBW:POW? >1.33e+01	

:CALCulate:OCBW:PSD?

→ **Query**

Description	Returns the OCBW power spectral density.	
Query Syntax	:CALCulate:OCBW:PSD?	
Return parameter	<NR3>	PSD in dBm/Hz.
Example	:CALC:OCBW:PSD? >9.933e+01	

Set →

:CALCulate:P1DB:STATe

→ **Query**

Description	Turns the P1DB function on or off.	
Syntax	:CALCulate:P1DB:STATe {ON OFF 1 0}	
Query Syntax	:CALCulate:P1DB:STATe?	
Parameter	OFF 0	Turns limits off.
	ON 1	Turns limits on.
Return parameter	0	Turns limits off.
	1	Turns limits on.
Example	:CALC:P1DB:STAT? >0	

:CALCulate:P1DB:GAIN:AVERage?



Description	Returns the P1dB average gain.	
Query Syntax	:CALCulate:P1DB:GAIN:AVERage?	
Return parameter	<NR3>	Return the average gain in dB.
	N/A	Returns N/A if the P1dB value is not found or not applicable.
Example	:CALC:P1DB:GAIN:AVER? >1.416e+01	

:CALCulate:P1DB:GAIN:RESult?



Description	Returns the gain (in dB) for each 1dBm increase in TG input level from -30dBm to 0dBm.
Query Syntax	:CALCulate:P1DB:GAIN:RESult?
Return parameter	<NR3>,<NR3>.....<NR3> (31 return values)
	<div style="display: flex;"> <div style="flex: 1; background-color: #cccccc; padding: 5px;"><div style="background-color: white; padding: 2px 5px;"><NR3></div></div> <div style="flex: 2; padding: 5px;">Gain in dB. Starting at -30dBm and ending at 0dBm</div> </div>
Example	:CALC:P1DB:GAIN:RES? >0.00e+00,0.00e+00,0.00e+00,0.00e+00,0.00e+00,0.00 e+00,0.00e+00,0.00e+00,0.00e+00,0.00e+00,0.00e+00, 0.00e+00,0.00e+00,0.00e+00,0.00e+00,0.00e+00,0.00e +00,0.00e+00,0.00e+00,0.00e+00,1.382e+01,1.406e+01 ,1.401e+01,1.404e+01,1.423e+01,1.419e+01,1.434e+01 ,1.441e+01,1.449e+01,1.460e+01,1.426e+01\n

:CALCulate:P1DB:RESult?



Description	Returns the P1dB result as x-y coordinates.
Query Syntax	:CALCulate:P1DB:RESult?

Return parameter	<x>,<y>	
	<x>	Returns the x-axis coordinate in dBm.
	<y>	Returns the y-axis coordinate in dBm.
Example	:CALC:P1DB:RES? >-9.25e+00,4.12e+00	

:CALCulate:PMETer:POWer? → Query

Description	Returns the power meter power measurement.	
Query Syntax	:CALCulate:PMETer:POWer?	
Return parameter	<NR3>	Power in the current Y-axis unit.
Example	:CALC:PMET:POW? >-0.83e+01	

:CALCulate:PMETer:LIMit:STATe Set → → Query

Description	Turns the pass/fail limits on/off in the Power Meter mode or queries its state.	
Syntax	:CALCulate:PMETer:LIMit:STATe {ON OFF 1 0}	
Query Syntax	:CALCulate:PMETer:LIMit:STATe?	
Parameter	0	Turns limits off.
	1	Turns limits on.
	OFF	Turns limits off.
	ON	Turns limits on.
Return parameter	0	Turns limits off.
	1	Turns limits on.
Example	:CALC:PMET:LIM:STAT? >1	

:CALCulate:PMETer:LIMit:FAIL? → Query


Description	Returns the pass/fail judgment.
-------------	---------------------------------

Query Syntax	:CALCulate:PMETER:LIMit:FAIL?	
Return parameter	0	Pass, or limits are not on.
	1	Fail
Example	:CALC:PMET:LIM:FAIL? >1	




:CALCulate:SEM:STATe

Description	Turns the SEM measurement on/off or queries its state.	
Syntax	:CALCulate:SEM:STATe {ON OFF 1 0}	
Query Syntax	:CALCulate:SEM:STATe?	
Parameter	0	Turns SEM off.
	1	Turns SEM on.
	OFF	Turns SEM off.
	ON	Turns SEM on.
Return parameter	0	SEM is off.
	1	SEM is on.
Example	:CALC:SEM:STAT ON	

:CALCulate:SEM:OFFSet<n>:RESult? 

Description	Returns the start, stop frequencies as well as the pass/fail limits and judgements for the chosen offset.	
Query syntax	:CALCulate:SEM:OFFSet<n>:RESult?	
Parameter	<n>	Offset number 1~5.
Return parameter	<start freq>	Start frequency of the selected channel
	<low dBm>	Lower dBm measurement
	<low p/f>	Lower pass/fail limit judgment. 0 = pass, 1 = fail.
	<stop freq>	Stop frequency of the selected channel
	<upp dBm>	Upper dBm measurement

	<upp p/f> Upper pass/fail limit judgment 0 = pass, 1 = fail.
Example	:CALC:SEM:OFFS1:RES? >9e+7, -7.9e+1,0,1.7e+7,-6.9e+1,0

:CALCulate:TOI:DIFFerential?

→ Query

Description	Returns the third order intermodulation distortion.	
Query syntax	:CALCulate:TOI:DIFFerential?	
Return parameter	<base lower>	<NR3> dBc
	<base upper>	<NR3> dBc
	<3 rd order lower>	<NR3> dBc
	<3 rd order upper>	<NR3> dBc
Example	:CALC:TOI:DIFF? >0.0e+0,-1.67e-1,-1.09e+1,-6.61e+0	

:CALCulate:TOI:FREQuency:DIFFerential?

→ Query

Description	Returns the delta of the base lower frequency and base upper frequency.	
Query syntax	:CALCulate:TOI:FREQuency:STEPsize?	
Return parameter	<NR3>	Δf : Hz
Example	:CALC:TOI:FREQ:DIFF? >6.65e+5	

Set →

:CALCulate:TOI:LIMit:STATe

→ Query

Description	Turns the TOI pass/fail limit on/off or queries its state.	
Syntax	:CALCulate:TOI:LIMit:STATe {ON OFF 1 0}	
Query Syntax	:CALCulate:TOI:LIMit:STATe?	
Parameter	0	Turns pass/fail limit off.
	1	Turns pass/fail limit on.

	OFF	Turns pass/fail limit off.
	ON	Turns pass/fail limit on.
Return parameter	0	Turns pass/fail limit off.
	1	Turns pass/fail limit on.
Example	:CALC:TOI:LIM:STAT ON	

:CALCulate:TOI:RESult?→ **Query**

Description	Returns the third order intercept and the pass/fail judgments.	
Query syntax	:CALCulate:TOI:RESult?	
Return parameter	<3 rd lower>	3 rd order lower intercept
	<lower p/f>	3 rd order lower pass/fail judgment. 0=pass, 1=fail
	<3 rd upper>	3 rd order upper intercept
	<upper p/f>	3 rd order lower pass/fail judgment 0=pass, 1=fail
Example	:CALC:TOI:RES? >-5.5e+1,0, -6.61e+1,0	

Set →**:CALCulate:TOI:STATe**→ **Query**

Description	Turns TOI measurement on/off or queries its state.	
Syntax	:CALCulate:TOI:STATe {ON OFF 1 0}	
Query Syntax	:CALCulate:TOI:STATe?	
Parameter	0	Turns TOI measurement off.
	1	Turns TOI measurement on.
	OFF	Turns TOI measurement off.
	ON	Turns TOI measurement on.
Return parameter	0	TOI measurement is off.
	1	TOI measurement is on.
Example	:CALC:TOI:STAT ON	

CONFigure Commands

:CONFigure:MODE..... 116

:CONFigure:MODE

Set

→

←

Query

Description	Sets or queries the operating mode, spectrum or power meter.	
Syntax	:CONFigure:MODE {SA PMETer}	
Query Syntax	:CONFigure:MODE?	
Parameter/ Return parameter	<SA> <PMETer>	Spectrum mode Power meter mode
Example	:CONF:MODE SA	

DISPlay Commands

:DISPlay:BRIGhtness.....	118
:DISPlay:ENABle	118
:DISPlay:DEMod[:WINDow]:TRACe:X[:SCALe]	
:AUTO	119
:DISPlay:DEMod[:WINDow]:TRACe:X[:SCALe]	
:PDIVision.....	119
:DISPlay:DEMod[:WINDow]:TRACe:X[:SCALe]	
:RPOSition.....	120
:DISPlay:DEMod[:WINDow]:TRACe:X[:SCALe]	
:RVALue	120
:DISPlay:DEMod[:WINDow]:TRACe:Y[:SCALe]	
:AUTO	120
:DISPlay:DEMod[:WINDow]:TRACe:Y[:SCALe]	
:PDIVision.....	121
:DISPlay:DEMod[:WINDow]:TRACe:Y[:SCALe]	
:RPOSition.....	121
:DISPlay:DEMod[:WINDow]:TRACe:Y[:SCALe]	
:RVALue	122
:DISPlay[:WINDow]:NORMal.....	122
:DISPlay[:WINDow]:SPECtrogram.....	122
:DISPlay[:WINDow]:SPLit:NORMal:ALTErnate.....	123
:DISPlay[:WINDow]:SPLit:NORMal:ACTive	123
:DISPlay[:WINDow]:SPLit:SPECtrogram	123
:DISPlay[:WINDow]:SPLit:TOPO	123
:DISPlay[:WINDow]:TOPO.....	124
:DISPlay[:WINDow]:TOPO:MARK:PERCent?	124
:DISPlay[:WINDow]:TOPO:DELT:PERCent?.....	124
:DISPlay[:WINDow]:TRACe<n>:MODE.....	125
:DISPlay[:WINDow]:TRACE<n>:MODE	
:MAXHOLD?	125
:DISPlay[:WINDow]:TRACe:Y:DLINe.....	125
:DISPlay[:WINDow]:TRACe:Y:DLINe:STATe	126
:DISPlay[:WINDow]:TRACe:Y[:SCALe]:AUTO	126
:DISPlay[:WINDow]:TRACe:Y[:SCALe]:NRLevel	126
:DISPlay[:WINDow]:TRACe:Y[:SCALe]:NRPosition..	127
:DISPlay[:WINDow]:TRACe:Y[:SCALe]:PDIVision...	127
:DISPlay[:WINDow]:TRACe:Y[:SCALe]:POSition.....	128
:DISPlay[:WINDow]:TRACe:Y[:SCALe]:RLEVel	128
:DISPlay[:WINDow]:TRACe:Y[:SCALe]:RLEVel	

:OFFSet..... 128
:DISPlay[:WINDow]:TRACe:Y[:SCALe]:SPACing..... 129
:DISPlay[:WINDow]:TRACe:Y[:SCALe]:STATe..... 129
:DISPlay:SPECtrogram:DELTA:INVerse:TIME? 130

:DISPlay:BRIGhtness

Set

→

→

Query

Description	Sets or queries the LCD brightness level.	
Syntax	:DISPlay:BRIGhtness {HIGH MIDDLE LOW}	
Query Syntax	:DISPlay:BRIGhtness?	
Parameter/ Return parameter	<HIGH>	High brightness level
	<MIDDLE>	Mid brightness level
	<LOW>	Low brightness level
Example	:DISP:BRIG HIGH	

:DISPlay:ENABle

Set

→

→

Query

Description	Turns the LCD backlight on/off.	
Syntax	:DISPlay:ENABle {OFF ON 0 1}	
Query Syntax	:DISPlay:ENABle?	
Parameter	0	Turn LCD backlight off.
	1	Turn LCD backlight on.
	OFF	Turn LCD backlight off.
	ON	Turn LCD backlight on.
Return parameter	0	LCD backlight is off.
	1	LCD backlight is on.
Example	:DISP:ENAB? >1	


```
:DISPlay:DEMod[:WINDow]:TRACe:X
[:SCALe]:AUTO
```

Set →
→ Query

Description	Turns auto scale on/off for AM/FM demodulation or queries its state. When set to ON, the auto scale function will be executed continuously.	
Syntax	:DISPlay:DEMod[:WINDow]:TRACe:X[:SCALe]:AUTO {OFF ON 0 1}	
Query Syntax	:DISPlay:DEMod[:WINDow]:TRACe:X[:SCALe]:AUTO?	
Parameter	0 1 OFF ON	Turn Auto Scale off. Turn Auto Scale on. Turn Auto Scale off. Turn Auto Scale on.
Return parameter	0 1	Auto Scale is off. Auto Scale is on.
Example	:DISP:DEM:TRAC:X:AUTO ON	

```
:DISPlay:DEMod[:WINDow]:TRACe:X
[:SCALe]:PDIVision
```

Set →
→ Query

Description	Sets or queries the time axis scale/div.	
Syntax	:DISPlay:DEMod[:WINDow]:TRACe:X[:SCALe]:PDIVision <time>	
Query Syntax	:DISPlay:DEMod[:WINDow]:TRACe:X[:SCALe]:PDIVision?	
Parameter	<time>	<NRf>
Return parameter	<NR3>	Seconds
Example	:DISP:DEM:TRAC:X:PDIV 2 ms	

```
:DISPlay:DEMod[:WINDow]:TRACe:X
[:SCALe]:RPOSition
```

Set →
→ Query

Description Sets or queries the Reference Position of the trace for AM/FM demodulation (x-axis grid division).

Syntax :DISPlay:DEMod[:WINDow]:TRACe:X[:SCALe]:RPOSition <integer>

Query Syntax :DISPlay:DEMod[:WINDow]:TRACe:X[:SCALe]:RPOSition?

Parameter/Return parameter <integer> <NR1>1~10

Example :DISP:DEM:TRAC:X:RPOS 2

```
:DISPlay:DEMod[:WINDow]:TRACe:X
[:SCALe]:RVALue
```

Set →
→ Query

Description Sets or queries the Reference value time.

Syntax :DISPlay:DEMod[:WINDow]:TRACe:X[:SCALe]:RVALue <time>

Query Syntax :DISPlay:DEMod[:WINDow]:TRACe:X[:SCALe]:RVALue?

Parameter <time> <NRf>

Return parameter <NR3> Seconds

Example :DISP:DEM:TRAC:X:RVAL 2 ms

```
:DISPlay:DEMod[:WINDow]:TRACe:Y
[:SCALe]:AUTO
```



Set →

Description Sets the vertical display scale to auto for AM/FM demodulation.

Syntax :DISPlay:DEMod[:WINDow]:TRACe:Y[:SCALe]:AUTO



Example :DISP:DEM:TRAC:Y:AUTO

:DISPlay:DEMod[:WINDow]:TRACe:Y
 [:SCALe]:PDIVision

Description	Sets or queries the Y-axis scale per division.	
Syntax	:DISPlay:DEMod[:WINDow]:TRACe:Y[:SCALe]:PDIVision <NRf>	
Query Syntax	:DISPlay:DEMod[:WINDow]:TRACe:Y[:SCALe]:PDIVision?	
Parameter	<NRf>	AM Unit: %, FM Unit: Hz
Return parameter	<NR3>	AM Unit: %, FM Unit: Hz
Example	:DISP:DEM:TRAC:Y:PDIV 2.3e+1	

:DISPlay:DEMod[:WINDow]:TRACe:Y
 [:SCALe]:RPOSition

Description	Sets or queries the Reference Position of the trace for AM/FM demodulation (y-axis grid division).	
Syntax	:DISPlay:DEMod[:WINDow]:TRACe:Y[:SCALe]:RPOSition <integer>	
Query Syntax	:DISPlay:DEMod[:WINDow]:TRACe:Y[:SCALe]:RPOSition?	
Parameter/ Return parameter	<integer>	<NR1>1~10
Example	:DISP:DEM:TRAC:Y:RPOS 2	

:DISPlay:DEMod[:WINDow]:TRACe:Y
[:SCALe]:RVALue

Set →
→ Query

Description	Sets or queries the Reference value (AM: %, FM: Hz).	
Syntax	:DISPlay:DEMod[:WINDow]:TRACe:Y[:SCALe]:RVALue <NRf>	
Query Syntax	:DISPlay:DEMod[:WINDow]:TRACe:Y[:SCALe]:RVALue?	
Parameter	<NRf>	AM Unit: %, FM Unit: Hz
Return parameter	<NR3>	AM Unit: %, FM Unit: Hz
Example	:DISP:DEM:TRAC:Y:RVAL 2 %	

:DISPlay[:WINDow]:NORMal

Set →

Description	Sets the display window to the normal trace mode.	
Syntax	:DISPlay[:WINDow]:NORMal	
Example	:DISP:NORM	

:DISPlay[:WINDow]:SPECtrogram

Set →

Description	Sets the display window to spectrogram mode.	
Syntax	:DISPlay[:WINDow]:SPECtrogram	
Example	:DISP:SPEC	

:DISPlay[:WINDow]:SPLit:NORMal:
ALternate

Set →

Description Turns on the Alternate Sweep function for split window mode, both windows are in the normal trace mode.
(we also have Spectrogram and Topographic mode)

Syntax :DISPlay[:WINDow]:SPLit:NORMal:ALternate

Example :DISP:SPL:NORM:ALT

:DISPlay[:WINDow]:SPLit:NORMal:ACTIVE

Set →

Description Sets which window (upper or lower) to display the normal trace mode in. It also becomes the active window. This command will also put the screen into split-screen mode if it is not already.

Syntax :DISPlay[:WINDow]:SPLit:NORMal:ACTIVE
{UPPer|LOWer}

Example :DISP:SPL:NORM:ACT UPP

:DISPlay[:WINDow]:SPLit:SPECTrogram

Set →

Description Sets the split screen mode to Spectrogram + Spectrum.

Syntax :DISPlay[:WINDow]:SPLit:SPECTrogram

Example :DISP:SPL:SPEC

:DISPlay[:WINDow]:SPLit:TOPO

Set →

Description Sets the split screen mode to Topographic + Spectrum.

Syntax	:DISPlay[:WINDow]:SPLit:TOPO
Example	:DISP:SPL:TOPO

:DISPlay[:WINDow]:TOPO

(Set) →

Description	Sets the display window to topographic.
Syntax	:DISPlay[:WINDow]:TOPO
Example	:DISP:TOPO

:DISPlay[:WINDow]:TOPO:MARK:PERCent?

→ (Query)

Description	Returns the percentage of traces that cross the reference marker position in the topographic display view.
Query syntax	:DISPlay[:WINDow]:TOPO:MARK:PERCent?
Return parameter	<NR3>
Example	:DISP:TOPO:MARK:PERC? >0.000e+00

:DISPlay[:WINDow]:TOPO:DELT:PERCent?

→ (Query)

Description	Returns the percentage of traces that cross the delta marker position in the topographic display view.
Query syntax	:DISPlay[:WINDow]:TOPO:DELT:PERCent?
Return parameter	<NR3>
Example	:DISP:TOPO:DELT:PERC? >6.667e+01

:DISPlay[:WINDow]:TRACe<n>:MODE Set →

Description	Sets the operation mode of the selected trace.	
Syntax	:DISPlay[:WINDow]:TRACe<n>:MODE {WRITe VIEW BLANK MAXHold MINHold}	
Parameter	<n> WRITe VIEW BLANK MAXHold MINHold	<NR1> Trace number 1~4 Clear and Write Hold the last trace Clears the trace Hold the maximum/minimum points from each sweep
Example	:DISP:TRAC4:MODE VIEW	



:DISPlay[:WINDow]:TRACE<n>:MODE:MAX
HOLD? Query

Description	Returns the maxhold threshold level. Any part of the trace below this threshold won't be held when the detector is set to Maxhold.	
Query syntax	:DISPlay[:WINDow]:TRACE<n>:MODE:MAXHOLD?	
Return parameter	<n> <NR3>	<NR1> Trace number.
Example	:DISP:TRACE2:MODE:MAXHOLD? >-2.000e+01	


:DISPlay[:WINDow]:TRACE:Y:DLINe Set →
Query

Description	Sets or queries the display line amplitude level.	
Syntax	:DISPlay[:WINDow]:TRACE:Y:DLINe <ampl>	
Query Syntax	:DISPlay[:WINDow]:TRACE:Y:DLINe?	



Parameter	<ampl>	<NRf> Power or voltage in the current Y-axis unit.
Return parameter	<NR3>	
Example	:DISP:TRAC:Y:DLIN -5.0e+01	

:DISPlay[:WINDow]:TRACe:Y:DLINe:STATe  

Description	Turns the display line on/off or queries its state.	
Syntax	:DISPlay[:WINDow]:TRACe:Y:DLINe:STATe {OFF ON 0 1}	
Query Syntax	:DISPlay[:WINDow]:TRACe:Y:DLINe:STATe?	
Parameter	0 1 OFF ON	Turn display line off. Turn display line on. Turn display line off. Turn display line on.
Return parameter	0 1	The display line is off. The display line is on.
Example	:DISP:TRAC:Y:DLIN:STAT ON	



:DISPlay[:WINDow]:TRACe:Y[:SCALE]:AUTO 

Description	Equivalent to Amplitude>Autoscale[F4] when operating via the front panel.	
Syntax	:DISPlay[:WINDow]:TRACe:Y[:SCALE]:AUTO {ONCE}	
Parameter	<ONCE>	Compulsory parameter.
Example	:DISP:TRAC:Y:AUTO ONCE	



:DISPlay[:WINDow]:TRACe:Y[:SCALE]:NRLevel  

Description	Sets or queries the normalized reference level for the TG option.	
-------------	---	--

Syntax	:DISPlay[:WINDow]:TRACe:Y[:SCALe]:NRLevel <ampl>	
Query Syntax	:DISPlay[:WINDow]:TRACe:Y[:SCALe]:NRLevel?	
Parameter	<ampl>	<NRf> Power or voltage in the current Y-axis unit.
Return parameter	<NR3>	
Example	:DISP:TRAC:Y:NRLevel 5 dBm	

:DISPlay[:WINDow]:TRACe:Y[:SCALe]:NRPosition  

Description	Sets or queries the position of the normalized reference level. The 0~10 Y-axis grid divisions correspond to the bottom~top grid divisions.	
Syntax	:DISPlay[:WINDow]:TRACe:Y[:SCALe]:NRPosition <integer>	
Query Syntax	:DISPlay[:WINDow]:TRACe:Y[:SCALe]:NRPosition?	
Parameter/ Return parameter	<integer>	<NR1> 0~10
Example	:DISP:TRAC:Y:NRP 5	

:DISPlay[:WINDow]:TRACe:Y[:SCALe]:PDIVision  

Description	Sets or queries the Y-axis scale/div when the amplitude scale is logarithmic.	
Syntax	:DISPlay[:WINDow]:TRACe:Y[:SCALe]:PDIVision{1 2 5 10}	
Query Syntax	:DISPlay[:WINDow]:TRACe:Y[:SCALe]:PDIVision?	
Parameter/ Return parameter	1	1 dB
	2	2 dB
	5	5 dB
	10	10 dB
Example	:DISP:TRAC:Y:PDIV 10	

**:DISPlay[:WINDow]:TRACe:Y[:SCALe]:
POSition**

Set →
→ Query

Description Sets or queries the position of the on-screen scale.

Syntax :DISPlay[:WINDow]:TRACe:Y[:SCALe]:POSition
{LEFT|CENTer|RIGHT}

Query Syntax :DISPlay[:WINDow]:TRACe:Y[:SCALe]:POSition?

Parameter/	LEFT	Position the scale to left
Return parameter	CENTer	Position the scale to the center
	RIGHT	Position the scale to right

Example :DISP:TRAC:Y:POS LEFT

**:DISPlay[:WINDow]:TRACe:Y[:SCALe]:
RLEVel**

Set →
→ Query

Description Sets or queries the Y-axis reference level. The units depend on the scale type (logarithmic/linear).

Syntax :DISPlay[:WINDow]:TRACe:Y[:SCALe]:RLEVel <ampl>

Query Syntax :DISPlay[:WINDow]:TRACe:Y[:SCALe]:RLEVel?

Parameter	<ampl>	<NRf>
Return parameter	<NR3>	

Example :DISP:TRAC:Y:RLEV 1 mV

**:DISPlay[:WINDow]:TRACe:Y[:SCALe]:
RLEVel:OFFSet**

Set →
→ Query

Description Sets or queries the Y-axis reference level offset.

Syntax :DISPlay[:WINDow]:TRACe:Y[:SCALe]:RLEVel:OFFSet
<rel_ampl>

Query Syntax :DISPlay[:WINDow]:TRACe:Y[:SCALe]:RLEVel:OFFSet?

Parameter	<ampl>	<NRf> dB
Return parameter	<NR3>	

Example :DISP:TRAC:Y:RLEV OFFS -5.0e+1 dB

:DISPlay[:WINDow]:TRACe:Y[:SCALe]:
SPACing

Description Sets or queries the type of scale: logarithmic or linear.

Syntax :DISPlay[:WINDow]:TRACe:Y[:SCALe]:SPACing
{LINear|LOGarithmic}

Query Syntax :DISPlay[:WINDow]:TRACe:Y[:SCALe]:SPACing?

Parameter/ LINear Linear scale

Return parameter LOGarithmic Logarithmic scale

Example :DISP:TRAC:Y:SPAC LOG

:DISPlay[:WINDow]:TRACe:Y[:SCALe]:
STATe

Description Turns the on-screen scale on/off or queries its state.

Syntax :DISPlay[:WINDow]:TRACe:Y[:SCALe]:STATe
{OFF|ON|0|1}

Query Syntax :DISPlay[:WINDow]:TRACe:Y[:SCALe]:STATe?

Parameter 0 Turn scale off.

1 Turn scale on.

OFF Turn scale off.

ON Turn scale on.

Return parameter 0 Scale is off.

1 Scale is on.

Example :DISP:TRAC:Y:STAT ON

:DISPlay:SPECTrogram:DELTA:INVerse:TIME?
E?




Description	Returns the frequency delta between the reference and delta marker in the spectrogram display view.	
Query syntax	:DISPlay:SPECTrogram:DELTA:INVerse:TIME?	
Return parameter	<NR3>	Returns the frequency delta in kHz.
Example	:DISP:SPEC:DELTA:INV:TIME? >1.233e+06	

INITiate Commands

:INITiate:CONTinuous	131
:INITiate[:IMMediate].....	131

:INITiate:CONTinuous



Description	Sets the sweep mode to continuous or single mode or queries its state.	
Syntax	:INITiate:CONTinuous {OFF ON 0 1}	
Query Syntax	:INITiate:CONTinuous?	
Parameter	0	single
	1	continuos
	OFF	single
	ON	continuos
Return parameter	0	single
	1	continuos
Example	:INIT:CONT ON	

:INITiate[:IMMediate]




Description	Initiates an immediate single sweep then stops the sweep.	
Syntax	:INITiate[:IMMediate]	
Example	:INIT	

INPut Commands


:INPut:ATTenuation.....	132
:INPut:ATTenuation:AUTO	132
:INPut:IMPedance.....	133
:INPut:OFFSet.....	133

:INPut:ATTenuation



Description	Sets or queries the input attenuation.	
Syntax	:INPut:ATTenuation <integer>	
Query Syntax	:INPut:ATTenuation?	
Parameter/ Return parameter	<integer>	<NR1> 0 to 50
Example	:INP:ATT 10 dB	

:INPut:ATTenuation:AUTO



Description	Sets or queries whether the automatic input attenuation is on/off.	
Syntax	:INPut:ATTenuation:AUTO {OFF ON 0 1}	
Query Syntax	:INPut:ATTenuation:AUTO?	
Parameter	0	Turn automatic input attenuation off.
	1	Turn automatic input attenuation on.
	OFF	Turn automatic input attenuation off.
	ON	Turn automatic input attenuation on.
Return parameter	0	Automatic input attenuation is off.
	1	Automatic input attenuation is on.
Example	:INP:ATT:AUTO ON	

:INPut:IMPedance

Set

→

→

Query

Description	Sets or queries the input impedance in Ω .	
Syntax	:INPut:IMPedance {50 75}	
Query Syntax	:INPut:IMPedance?	
Parameter/	50	<NR1> Ω
Return parameter	75	<NR1> Ω
Example	:INP:IMP 75	

:INPut:OFFSet

Set

→

→

Query

Description	Sets or queries the input offset (Input Z Calibration).	
Syntax	:INPut:OFFSet <rel_ampl>	
Query Syntax	:INPut:OFFSet?	
Parameter/	<rel_ampl>	<NR3> dB
Return parameter		
Example	:INP:OFFS 10 dB	

MMEMory Commands

:MMEMory:CATalog?	134
:MMEMory:CDIRectory	135
:MMEMory:COPI	135
:MMEMory:DELe	136
:MMEMory:DESTination	136
:MMEMory:LOAD:CORRection	137
:MMEMory:LOAD:LIMit	137
:MMEMory:LOAD:PMETer	137
:MMEMory:LOAD:SEQuence	137
:MMEMory:LOAD:STATe	138
:MMEMory:LOAD:TRACe	138
:MMEMory:MOVE	138
:MMEMory:REName	139
:MMEMory:STORe:CORRection	139
:MMEMory:STORe:LIMit	139
:MMEMory:STORe:PMETer	140
:MMEMory:STORe:SCReen	140
:MMEMory:STORe:SEQuence	140
:MMEMory:STORe:STATe	140
:MMEMory:STORe:TRACe	141

:MMEMory:CATalog? → **Query**

Description	Returns a list of all the files that have been saved to the local memory.
Query Syntax	:MMEMory:CATalog?
Example	:MMEM:CAT? >LocalState1.sta, QuickJpg.jpg,QuickJpg1.jpg,.....

:MMEMory:CDIRectory



Description	<p>Sets the source directory for memory related commands.</p> <p>When you use a single USB drive/SD card with multiple partitions inside, the system will automatically name these partitions in the numeric order, so you need to specify the partition number.</p> <p>The same situation applies when you use a USB hub to extend the number of USB ports. When a hub is used, <i>all</i> the partitions from <i>all</i> the attached devices are numbered in numerical order from the first port to the last port.</p> <p>If a partition number is not supplied, the system will default to partition #1. For example: :MMEM:CDI USB<u>0</u> = :MMEM:CDI USB)</p>	
Syntax	:MMEMory:CDIRectory {LOCAL USB[<n>] SD[<n>]}	
Parameter	LOCAL	
	USB<n>	<NR1>
	SD<n>	<NR1>
Example1	:MMEM:CDIR USB	
Example2	:MMEM:CDIR USB3	

:MMEMory:COPY



Description	<p>Copies a designated file from the current file directory to the destination directory. The file can be renamed after it is copied.</p>	
Syntax	:MMEMory:COPY <src_file_name>,<dest_file_name>	
Parameter	<src_file_name>	
	<dest_file_name>	
Example	:MMEM:COPY QuickJpg1.jpg,QuickJpg2.jpg	

:MMEMory:DELeTe

Set →

Description	Deletes the designated file from the current directory.
Syntax	:MMEMory:DELeTe <src_file_name>
Parameter	<src_file_name>
Example	:MMEM:DEL QuickJpg1.jpg

:MMEMory:DESTination

Set →

Description	<p>Sets the destination directory for memory related commands.</p> <p>When you use a single USB drive/SD card with multiple partitions inside, the system will automatically name these partitions in the numeric order, so you need to specify the partition number.</p> <p>The same situation applies when you use a USB hub to extend the number of USB ports. When a hub is used, <i>all</i> the partitions from <i>all</i> the attached devices are numbered in numerical order from the first port to the last port.</p> <p>If a partition number is not supplied, the system will default to partition #1. For example: :MMEM:DEST USB0 = :MMEM:DEST USB)</p>	
Syntax	:MMEMory:DESTination {LOCAL USB[<n>] SD[<n>]}	
Parameter	LOCAL	
	USB<n>	<NR1>
	SD<n>	<NR1>
Example	:MMEM:DEST SD	

:MMEMory:LOAD:CORRection**Set** →

Description	Loads correction data from a file to the internal memory.
-------------	---

Syntax	:MMEMory:LOAD:CORRection <corr num>,<src_file_name>
--------	---

Parameter	<corr num> <src_file_name>	<NR1> correction set 1~5 XXX.cor
-----------	-------------------------------	-------------------------------------

Example	:MMEM:LOAD:CORR 2,test.cor
---------	----------------------------

:MMEMory:LOAD:LIMit**Set** →

Description	Loads limit line data from a file to the internal memory.
-------------	---

Syntax	:MMEMory:LOAD:LIMit <lim num>,<src_file_name>
--------	---

Parameter	<lim num> <src_file_name>	<NR1> limit line 1~5 XXX.lim
-----------	------------------------------	---------------------------------

Example	:MMEM:LOAD:LIM 2,test.lim
---------	---------------------------

:MMEMory:LOAD:PMETer**Set** →

Description	Loads power meter data from a file to the internal memory.
-------------	--

Syntax	:MMEMory:LOAD:PMETer <src_file_name>
--------	--------------------------------------

Parameter	<src_file_name>	XXX.pmet
-----------	-----------------	----------

Example	:MMEM:LOAD:PMET test.pmet
---------	---------------------------

:MMEMory:LOAD:SEQuence**Set** →

Description	Loads sequence data from a file to the internal memory.
-------------	---

Syntax	:MMEMory:LOAD:SEQuence <seq num>, <src_file_name>	
Parameter	<seq num> <src_file_name>	<NR1>sequence number 1~5 XXX.seq
Example	:MMEM:LOAD:SEQ 2,test.seq	

:MMEMory:LOAD:STATe



Description	Loads the instrument state from a file to the internal memory.	
Syntax	:MMEMory:LOAD:STATe <src_file_name>	
Parameter	<src_file_name>	XXX.stat
Example	:MMEM:LOAD:STAT test.stat	

:MMEMory:LOAD:TRACe



Description	Loads trace data from a file to the internal memory.	
Syntax	:MMEMory:LOAD:TRACe <trace name>, <src_file_name>	
Parameter	<trace name> <src_file_name>	<NR1> 1~4 XXX.tra
Example	:MMEM:LOAD:TRAC 2,test.tra	

:MMEMory:MOVE



Description	Moves a designated file from the current file directory to the destination directory. The file can be renamed after it is moved.	
Syntax	:MMEMory:MOVE <src_file_name>,<dest_file_name>	
Parameter	<src_file_name> <dest_file_name>	

Example :MMEM:MOVE QuickJpg1.jpg,QuickJpg2.jpg

:MMEMory:REName

(Set) →

Description Renames the designated file from the current file.

Syntax :MMEMory:REName
<old_file_name>,<new_file_name>

Parameter <old_file_name>
<new_file_name>

Example :MMEM:REN QuickJpg1.jpg,QuickJpg2.jpg

:MMEMory:STOR:CORRection

(Set) →

Description Store correction data to a file from the internal memory.

Syntax :MMEMory:STOR:CORRection
<corr num>,<new_dest_file_name>

Parameter <corr num> <NR1> correction set 1~5
<new_dest_file_name> XXX.cor

Example :MMEM:STOR:CORR 2,test.cor

:MMEMory:STOR:LIMit

(Set) →

Description Store limit line data to a file from the internal memory.

Syntax :MMEMory:STOR:LIMit
<lim num>,<new_dest_file_name>

Parameter <lim num> <NR1> limit line 1~5
<new_dest_file_name> XXX.lim

Example :MMEM:STOR:LIM 2,test.lim

:MMEMory:STORe:PMETer

(Set) →

Description Store power meter data to a file from the internal memory.

Syntax :MMEMory:STORe:PMETer <new_dest_file_name>

Parameter <new_dest_file_name> XXX.pmet

Example :MMEM:STOR:PMET test.pmet

:MMEMory:STORe:SCReen

(Set) →

Description Store a screen-shot to the current file directory.

Syntax :MMEMory:STORe:SCReen <new_dest_file_name>

Parameter <new_dest_file_name> XXX.jpg

Example :MMEM:STOR:SCR test.jpg

:MMEMory:STORe:SEQuence

(Set) →

Description Store sequence data to a file from the internal memory.

Syntax :MMEMory:STORe:SEQuence <seq num>, <new_dest_file_name>

Parameter <seq num> <NR1>sequence number
1~5
<new_dest_file_name> XXX.seq

Example :MMEM:STOR:SEQ 2,test.seq

:MMEMory:STORe:STATe

(Set) →

Description Store the instrument state to a file from the internal memory.

Syntax :MMEMory:STORe:STATe <new_dest_file_name>

Parameter	<new_dest_file_name>	XXX.stat
Example	:MMEM:STORe:STAT test.stat	

:MMEMory:STORe:TRACe



Description	Store trace data to a file from the internal memory.	
Syntax	:MMEMory:STORe:TRACe <trace name>, <new_dest_file_name>	
Parameter	<trace name> <new_dest_file_name>	<NR1> 1~4 XXX.tra
Example	:MMEM:STORe:TRAC 2,test.tra	

OUTPut Commands

:OUTPut[:STATe] 142

:OUTPut[:STATe]

Set

→

→

Query

Description	Turns the tracking generator output on/off or queries its state.	
Syntax	:OUTPut[:STATe] {OFF ON 0 1}	
Query Syntax	:OUTPut[:STATe]?	
Parameter	0	Turn TG output off.
	1	Turn TG output on.
	OFF	Turn TG output off.
	ON	Turn TG output on.
Return parameter	0	TG output is off.
	1	TG output is on.
Example	:OUTP ON	



SENSe Commands

[SENSe]:ACPR:ACHannel<n>	
:BANDwidth BWIDth	146
[SENSe]:ACPR:ACHannel<n>:HLIMit	146
[SENSe]:ACPR:ACHannel<n>:LLIMit	147
[SENSe]:ACPR:ACHannel<n>:OFFSet	147
[SENSe]:ACPR:BANDwidth BWIDth	147
[SENSe]:ACPR:HLIMit	148
[SENSe]:ACPR:LLIMit	148
[SENSe]:ACPR:HELP:STATe	148
[SENSe]:ACPR:SPACe	149
[SENSe]:ASET:AMPLitude	149
[SENSe]:ASET:AMPLitude:AUTO	149
[SENSe]:ASET:RUN	150
[SENSe]:ASET:SPAN	150
[SENSe]:ASET:SPAN:AUTO	150
[SENSe]:AVERage:COUNt	151
[SENSe]:AVERage:STATe	151
[SENSe]:AVERage:TYPE	151
[SENSe]:BANDwidth BWIDth[:RESolution]	152
[SENSe]:BANDwidth BWIDth[:RESolution]:AUTO	152
[SENSe]:BANDwidth BWIDth:VIDeo	153
[SENSe]:BANDwidth BWIDth:VIDeo:AUTO	153
[SENSe]:CHANnel:SPACe:DOWN	153
[SENSe]:CHANnel:SPACe:UP	154
[SENSe]:CNR:CHANnel:SPACe	154
[SENSe]:CNR:DELTamarker:MODE	154
[SENSe]:CORRection:CSET<n>:DATA	155
[SENSe]:CORRection:CSET<n>:STATe	155
[SENSe]:CORRection:CSET<n>:DELeTe	156
[SENSe]:CSO:CHANnel:SPACe	156
[SENSe]:CTB:CHANnel:SPACe	156
[SENSe]:DEMod:EARPhone:TYPE	157
[SENSe]:DEMod:EARPhone:VOLume	157
[SENSe]:DEMod:EARPhone:GAIN	157
[SENSe]:DEMod:FILTer:LPASs	158
[SENSe]:DEMod:IFBW	158
[SENSe]:DEMod:SQUelch:LEVel	159
[SENSe]:DETeCTOR[:FUNCTION]	159
[SENSe]:DETeCTOR[:FUNCTION]:AUTO	159



[SENSe]:EMIFilter:STATe	160
[SENSe]:EMIFilter:BANDwidth BWIDth	
[RESolution]	160
[SENSe]:FREQuency:CENTer	161
[SENSe]:FREQuency:CENTer:STEP	161
[SENSe]:FREQuency:CENTer:STEP:AUTO	161
[SENSe]:FREQuency:OFFSet	162
[SENSe]:FREQuency:SPAN	162
[SENSe]:FREQuency:SPAN:FULL	162
[SENSe]:FREQuency:SPAN:PREVious	162
[SENSe]:FREQuency:STARt	163
[SENSe]:FREQuency:STOP	163
[SENSe]:HARMonic:FUNDamental:FREQuency	163
[SENSe]:HARMonic:NUMBer	164
[SENSe]:LIMit<n>:DELeTe	164
[SENSe]:JITTer:OFFSet:STARt	164
[SENSe]:JITTer:OFFSet:STOP	164
[SENSe]:NDB:BANDwidth BWIDth	165
[SENSe]:OCBW:BANDwidth BWIDth	165
[SENSe]:OCBW:PERCent	165
[SENSe]:OCBW:SPACe	166
[SENSe]:P1DB:AVERAge:COUNt	166
[SENSe]:P1DB:GAIN:OFFSet	166
[SENSe]:PMETer:FREQuency	167
[SENSe]:PMETer:HLIMit	167
[SENSe]:PMETer:HOLD:STATe	167
[SENSe]:PMETer:LLIMit	168
[SENSe]:PMETer:PSEnSor:MODE	168
[SENSe]:PMETer:RECORDing:TIME	168
[SENSe]:PMETer:RECORDing:TIME:STEP	169
[SENSe]:POWEr[:RF]:GAIN	169
[SENSe]:SEMask:BANDwidth BWIDth:INTegration	170
[SENSe]:SEMask:BANDwidth BWIDth	
[RESolution]	170
[SENSe]:SEMask:BANDwidth BWIDth	
[RESolution]:AUTO	170
[SENSe]:SEMask:CARRier:AUTO	171
[SENSe]:SEMask:CARRier:CPSD	171
[SENSe]:SEMask:CARRier:POWEr	172
[SENSe]:SEMask:FREQuency:SPAN	172
[SENSe]:SEMask:GWLan:MODulation	172
[SENSe]:SEMask:HELP:STATe	173
[SENSe]:SEMask:NWLan:CHANnel:	

BANDwidth BWIDth	173
[;SENSe];SEMask:OFFSet<n>:ADDition:	
BANDwidth BWIDth[:RESolution]?	174
[;SENSe];SEMask:OFFSet<n>:ADDition:	
FREQuency:STARt?	176
[;SENSe];SEMask:OFFSet<n>:ADDition:	
FREQuency:STOP?	176
[;SENSe];SEMask:OFFSet<n>:ADDition:	
STARt:ABSolute?	177
[;SENSe];SEMask:OFFSet<n>:ADDition:	
STOP:ABSolute?	177
[;SENSe];SEMask:OFFSet<n>:BANDwidth	
BWIDth[:RESolution]	177
[;SENSe];SEMask:OFFSet<n>:BANDwidth BWIDth	
[:RESolution]:AUTO	178
[;SENSe];SEMask:OFFSet<n>:FREQuency:STARt	178
[;SENSe];SEMask:OFFSet<n>:FREQuency:STOP	179
[;SENSe];SEMask:OFFSet<n>:STARt:ABSolute	179
[;SENSe];SEMask:OFFSet<n>:STARt:RELative	179
[;SENSe];SEMask:OFFSet<n>:STATe	180
[;SENSe];SEMask:OFFSet<n>:STOP:ABSolute	180
[;SENSe];SEMask:OFFSet<n>:STOP:ABSolute	
:COUPle	181
[;SENSe];SEMask:OFFSet<n>:STOP:RELative	181
[;SENSe];SEMask:OFFSet<n>:STOP:RELative	
:COUPle	182
[;SENSe];SEMask:OFFSet<n>:TEST	182
[;SENSe];SEMask:SELEct	182
[;SENSe];SEMask:TYPE	183
[;SENSe];SEMask:W3GPP:DUPLex:TYPE	183
[;SENSe];SEMask:W3GPP:FDD:ADDition:LIMit	184
[;SENSe];SEMask:W3GPP:FDD:ADDition	
:MOPower	184
[;SENSe];SEMask:W3GPP:FDD:MOPower	184
[;SENSe];SEMask:W3GPP:FDD:TRANsmiT:MODE	185
[;SENSe];SEMask:W3GPP:TDD:CHIP:RATE	185
[;SENSe];SEMask:W3GPP:TDD:MOPower	186
[;SENSe];SEMask:W3GPP:TDD:TRANsmiT:MODE	186
[;SENSe];SEMask:WIMax:CHANnel:	
BANDwidth BWIDth	187
[;SENSe];SEQuence<n>:DELete	187
[;SENSe];SWEep:EGATe:DELay	187
[;SENSe];SWEep:EGATe:LENGth	188



[[:SENSe]:SWEp:EGATe:STATe.....	188
[[:SENSe]:SWEp:MODE.....	188
[[:SENSe]:SWEp:TIME	189
[[:SENSe]:SWEp:TIME:AUTO.....	189
[[:SENSe]:TOI:REFeRence	189
[[:SENSe]:TOI:LIMit.....	190

[[:SENSe]:ACPR:ACHannel<n>:BANDwidth| BWIDth  

Description	Sets or queries the adjacent channel bandwidth for the selected adjacent channel. Used with ACPR measurement.	
Syntax	[:SENSe]:ACPR:ACHannel<n>:BANDwidth BWIDth <freq>	
Query Syntax	[:SENSe]:ACPR:ACHannel<n>:BANDwidth BWIDth?	
Parameter	<freq>	<NRf>
Return parameter	<NR3>	Hz
Example	:ACPR:ACH1:BAND 2.0e+6	

[[:SENSe]:ACPR:ACHannel<n>:HLIMit  

Description	Sets or queries the high limit for the selected adjacent channel. Used with ACPR measurement.	
Syntax	[:SENSe]:ACPR:ACHannel<n>:HLIMit <ampl>	
Query Syntax	[:SENSe]:ACPR:ACHannel<n>:HLIMit?	
Parameter	<ampl>	<NRf> power or voltage
Return parameter	<NR3>	
Example	:ACPR:ACH1:HLIM -3.0e+1	

[:SENSe]:ACPR:ACHannel<n>:LLIMit  

Description Sets or queries the low limit for the selected adjacent channel. Used with ACPR measurement.

Syntax [:SENSe]:ACPR:ACHannel<n>:LLIMit <ampl>

Query Syntax [:SENSe]:ACPR:ACHannel<n>:LLIMit?

Parameter <ampl> <NRf3> power or voltage

Return parameter <NR3>

Example :ACPR:ACH1:LLIM -5.0e+1

[:SENSe]:ACPR:ACHannel<n>:OFFSet  

Description Sets or queries the adjacent channel offset for the selected adjacent channel. Used with ACPR measurement.

Syntax [:SENSe]:ACPR:ACHannel<n>:OFFSet <freq>

Query Syntax [:SENSe]:ACPR:ACHannel<n>:OFFSet?

Parameter <freq> <NRf>

Return parameter <NR3> Hz

Example :ACPR:ACH1:OFFSet 2.0e+6

[:SENSe]:ACPR:BANDwidth|BWIDth  

Description Sets or queries the main channel bandwidth for ACPR measurements.

Syntax [:SENSe]:ACPR:BANDwidth|BWIDth <freq>

Query Syntax [:SENSe]:ACPR:BANDwidth|BWIDth?

Parameter <freq> <NRf>

Return parameter <NR3> Hz

Example :ACPR: BAND 2.0e+6

Set

Query

[:SENSe]:ACPR:HLIMit	
Description	Sets or queries the high limit for the main channel. Used with ACPR measurement.
Syntax	[:SENSe]:ACPR:HLIMit <ampl>
Query Syntax	[:SENSe]:ACPR:HLIMit?
Parameter	<ampl> <NRf> power or voltage
Return parameter	<NR3>
Example	:ACPR: HLIM -3.0e+1

Set

Query

[:SENSe]:ACPR:LLIMit	
Description	Sets or queries the low limit for the main channel. Used with ACPR measurement.
Syntax	[:SENSe]:ACPR:LLIMit <ampl>
Query Syntax	[:SENSe]:ACPR:LLIMit?
Parameter	<ampl> <NRf> power or voltage
Return parameter	<NR3>
Example	:ACPR:ACH1:LLIM -5.0e+1

Set

[:SENSe]:ACPR:HELP:STATe	
Description	Turns the on-screen help on/off.
Syntax	[:SENSe]:ACPR:HELP:STATe {OFF ON 0 1}
Parameter	0 Turn help off. 1 Turn help on. OFF Turn help off. ON Turn help on.
Example	:ACPR:HELP:STAT ON

[:SENSe]:ACPR:SPACe

Set →

→ Query

Description Sets or queries the channel spacing between the main channels.

Syntax [:SENSe]:ACPR:SPACe <freq>

Query Syntax [:SENSe]:ACPR:SPACe?

Parameter <freq> <NRf>

Return parameter <NR3> Hz

Example :ACPR: SPAC 2.0e+6

[:SENSe]:ASET:AMPLitude

Set →

→ Query

Description Sets or queries the autoset amplitude floor level.

Syntax [:SENSe]:ASET:AMPLitude <ampl>

Query Syntax [:SENSe]:ASET:AMPLitude?

Parameter <ampl> <NRf> power or voltage

Return parameter <NR3>

Example :ASET:AMPL 8.0e+1

[:SENSe]:ASET:AMPLitude:AUTO

Set →

→ Query

Description Sets autoset amplitude floor level to auto or manual or queries its state.

Syntax [:SENSe]:ASET:AMPLitude:AUTO {OFF|ON|0|1}

Query Syntax [:SENSe]:ASET:AMPLitude:AUTO?

Parameter	0	Turn autoset amplitude floor to manual.
	1	Turn autoset amplitude floor to auto.
	OFF	Turn autoset amplitude floor to manual.
	ON	Turn autoset amplitude floor to auto.

Return parameter	0	Autoset amplitude floor is in manual.
	1	Autoset amplitude floor is in auto.
Example	:ASET:AMPL:AUTO 1	

[[:SENSE]:ASET:RUN

Set →

Description	Activates the Autoset function.	
Syntax	[:SENSE]:ASET:RUN	
Example	:ASET:RUN	

[[:SENSE]:ASET:SPAN

Set →

→ **Query**

Description	Sets or queries the Autoset span.	
Syntax	[:SENSE]:ASET:SPAN <freq>	
Query Syntax	[:SENSE]:ASET:SPAN?	
Parameter	<freq>	<NRf>
Return parameter	<NR3>	Hz
Example	ASET:SPAN 2.0e+6	

[[:SENSE]:ASET:SPAN:AUTO

Set →

→ **Query**

Description	Turns the Autoset span to auto or manual or queries its state.	
Syntax	[:SENSE]:ASET:SPAN:AUTO {OFF ON 0 1}	
Query Syntax	[:SENSE]:ASET:SPAN:AUTO?	
Parameter	0	Turn Autoset span to manual (off).
	1	Turn Autoset span to automatic (on).
	OFF	Turn Autoset span to manual (off).
	ON	Turn Autoset span to automatic (on).
Return parameter	0	Autoset span is set to manual (off).
	1	Autoset span is set to automatic (on).

Example :ASET:SPAN:AUTO

[[:SENSe]:AVERage:COUNT

Set →

→ Query

Description Sets or queries the number of traces that are used with the average function.

Syntax [[:SENSe]:AVERage:COUNT <integer>

Query Syntax [[:SENSe]:AVERage:COUNT?

Parameter/
Return parameter <integer> <NR1>

Example :AVER:COUN 20

[[:SENSe]:AVERage:STATe

Set →

→ Query

Description Turns the Average function on/off or queries its state.

Syntax [[:SENSe]:AVERage:STATe {OFF|ON|0|1}

Query Syntax [[:SENSe]:AVERage:STATe?

Parameter	0	Turn the Average function off.
	1	Turn the Average function on.
	OFF	Turn the Average function off.
	ON	Turn the Average function on.

Return parameter	0	The Average function is off.
	1	The Average function is on.

Example :AVER:STAT ON

[[:SENSe]:AVERage:TYPE

Set →

Description Sets the method that the Average function uses to calculate the average.



Syntax [[:SENSe]:AVERage:TYPE
{VOLTage|LOGarithmic|POWER}

Query syntax	[:SENSe]:AVERage:TYPE?	
Parameter/Return parameter	VOLTage	Sets Average to voltage
	LOGarithmic	Sets Average to logarithmic
	POWER	Sets Average to power
Example	:AVER:TYPE VOLT	




[:SENSe]:BANDwidth|BWIDth[:RESolution]

Description	Sets or queries the resolution bandwidth (RBW).	
Syntax	[:SENSe]:BANDwidth BWIDth[:RESolution] <freq>	
Query Syntax	[:SENSe]:BANDwidth BWIDth[:RESolution]?	
Parameter	<freq>	<NRf>
Return parameter	<NR3>	Hz
Example	:BAND 1.0e+6	

[:SENSe]:BANDwidth|BWIDth[:RESolution]:AUTO

Description	Turns the RBW to auto (on) or manual (off) or queries its state.	
Syntax	[:SENSe]: BANDwidth BWIDth[:RESolution]:AUTO {OFF ON 0 1}	
Query Syntax	[:SENSe]: BANDwidth BWIDth[:RESolution]:AUTO?	
Parameter	0	Turn RBW to manual (off).
	1	Turn RBW to automatic (on).
	OFF	Turn RBW to manual (off).
	ON	Turn RBW to automatic (on).
Return parameter	0	RBW is set to manual (off).
	1	RBW is set to automatic (on).
Example	:BAND:AUTO ON	

[:SENSe]:BANDwidth|BWIDth:VIDeo (Set) →
→ (Query)

Description	Sets or queries the video bandwidth (VBW).	
Syntax	[:SENSe]:BANDwidth BWIDth:VIDeo <freq>	
Query Syntax	[:SENSe]:BANDwidth BWIDth:VIDeo?	
Parameter	<freq>	<NRf>
Return parameter	<NR3>	Hz
Example	BAND:VID 1.0e+6	

[:SENSe]:BANDwidth|BWIDth:VIDeo:AUTO (Set) →
→ (Query)

Description	Turns the VBW to auto (on) or manual (off) or queries its state.	
Syntax	[:SENSe]:BANDwidth BWIDth:VIDeo:AUTO {OFF ON 0 1}	
Query Syntax	[:SENSe]:BANDwidth BWIDth:VIDeo:AUTO?	
Parameter	0 1 OFF ON	Turn VBW to manual (off). Turn VBW to automatic (on). Turn VBW to manual (off). Turn VBW to automatic (on).
Return parameter	0 1	VBW is set to manual (off). VBW is set to automatic (on).
Example	:BAND:VID:AUTO OFF	

[:SENSe]:CHANnel:SPACe:DOWN (Set) →

Description	Moves to the previous main channel when using measurements that have a channel space setting.
Syntax	[:SENSe]:CHANnel:SPACe:DOWN
Example	:CHAN:SPAC:DOWN

[:SENSe]:CHANnel:SPACe:UP

Set →

Description Moves to the next main channel when using measurements that have a channel space setting.

Syntax [:SENSe]:CHANnel:SPACe:UP

Example :CHAN:SPAC:UP

[:SENSe]:CNR:CHANnel:SPACe

Set →

→ Query

Description Sets or queries the channel space bandwidth for CNR measurements.

Syntax [:SENSe]:CNR:CHANnel:SPACe <freq>

Query Syntax [:SENSe]:CNR:CHANnel:SPACe?

Parameter <freq> <NRf>

Return parameter <NR3> Hz

Example :CNR:CHAN:SPAC 6.0e+6

[:SENSe]:CNR:DELTaMarker:MODE

Set →

Description Turns the CNR Noise Marking function to Min(AUTO) or ΔMarker(MANual).

Syntax [:SENSe]:CNR:DELTaMarker:MODE {AUTO|MANual }

Parameter AUTO Sets the Noise Marking to Min.
ΔMarker Sets the Noise Marking to ΔMarker.

Example :CNR:DELT:MODE AUTO

[[:SENSe]:CORRection:CSET<n>:DATA  

Description	<p>As a command, sets an offset for a certain frequency for a selected correction set.</p> <p>As a query, returns the data contents for the selected correction set as <csv data>. The data will be arranged as:</p> <p>pt#1 freq, pt#1 offset, pt#2 freq, pt#2 offset,...</p>	
Syntax	[:SENSe]:CORRection:CSET<n>:DATA <freq>,<offset>	
Query syntax	[:SENSe]:CORRection:CSET<n>:DATA?	
Parameter	<div><freq></div> <div><offset></div> <div><n></div>	<div><NRf> Hz</div> <div><NRf> dB</div> <div><NR1>correction set number</div>
Return parameter	<CSV data>	pt#1 freq, pt#1 offset,..... pt#n freq, pt#n offset
Example	CORR:CSET1:DATA 2e+6,30	

[[:SENSe]:CORRection:CSET<n>:STATe  

Description	Turns the selected correction set on/off or queries its state.	
Syntax	[:SENSe]:CORRection:CSET<n>:STATe {OFF ON 0 1}	
Query Syntax	[:SENSe]:CORRection:CSET<n>:STATe?	
Parameter	<div>0</div> <div>1</div> <div>OFF</div> <div>ON</div> <div><n></div>	<div>Turn turn the selected correction set off.</div> <div>Turn turn the selected correction set on.</div> <div>Turn turn the selected correction set off.</div> <div>Turn turn the selected correction set on.</div> <div><NR1>correction set number</div>
Return parameter	<div>0</div> <div>1</div>	<div>The selected correction set is off.</div> <div>The selected correction set is on.</div>
Example	:CORR:CSET1:STAT ON	

[[:SENSe]:CORRection:CSET<n>:DELeTe (Set) →

Description	Deletes the chosen correction set.
Syntax	[[:SENSe]:CORRection:CSET<n>:DELeTe
Parameter	<n> <NR1>correction set number
Example	:CORR:CSET1:DEL 2

[[:SENSe]:CSO:CHANnel:SPACe (Set) →
→ (Query)

Description	Sets the channel space bandwidth for CSO measurements.
Syntax	[[:SENSe]:CSO:CHANnel:SPACe <freq>
Query Syntax	[[:SENSe]:CSO:CHANnel:SPACe?
Parameter	<freq> <NRf>
Return parameter	<NR3> Hz
Example	:CSO:CHAN:SPAC 6.0e+6

[[:SENSe]:CTB:CHANnel:SPACe (Set) →
→ (Query)

Description	Sets the channel space bandwidth for CTB measurements.
Syntax	[[:SENSe]:CTB:CHANnel:SPACe <freq>
Query Syntax	[[:SENSe]:CTB:CHANnel:SPACe?
Parameter	<freq> <NRf>
Return parameter	<NR3> Hz
Example	:CTB:CHAN:SPAC 6.0e+6

[:SENSe]:DEMod:EARPhone:TYPE

Set →

→ Query

Description	Sets or queries the demodulation type for the Ear Phone Out demodulation function.
-------------	--

Syntax	[:SENSe]:DEMod:EARPhone:TYPE {AM FM}
--------	--------------------------------------

Query Syntax	[:SENSe]:DEMod:EARPhone:TYPE?
--------------	-------------------------------

Parameter	AM	AM demodulation
	FM	FM demodulation

Example	:DEM:EARP:TYPE AM
---------	-------------------

[:SENSe]:DEMod:EARPhone:VOLume

Set →

→ Query

Description	Sets or queries the volume setting for the demodulation function.
-------------	---

Syntax	[:SENSe]:DEMod:EARPhone:VOLume <integer>
--------	--

Query Syntax	[:SENSe]:DEMod:EARPhone:VOLume?
--------------	---------------------------------

Parameter/ Return parameter	<integer>	<NR1> 0~15
--------------------------------	-----------	------------

Example	:DEM:EARP:VOL 7
---------	-----------------

[:SENSe]:DEMod:EARPhone:GAIN

Set →

→ Query

Description	Sets or queries the gain setting for the demodulation function.
-------------	---

Syntax	[:SENSe]:DEMod:EARPhone:GAIN <rel_ampl>
--------	---

Query Syntax	[:SENSe]:DEMod:EARPhone:GAIN?
--------------	-------------------------------

Parameter/ Return parameter	<rel_ampl>	<NR1> 0~18, 6dB steps
--------------------------------	------------	-----------------------

Example	:DEM:EARP:GAIN 6
---------	------------------

Set →

→ Query

[[:SENSE]:DEMod:FILTer:LPASs

Description Sets or queries the low pass filter settings for the AM/FM Analysis function.

Syntax [[:SENSE]:DEMod:FILTer:LPASs {LEVEL<n>|Bypass}

Query Syntax [[:SENSE]:DEMod:FILTer:LPASs?

Parameter/Return parameter Bypass <n> Sets the low pass filter to bypass.
<NR1>1~5

The filters 1 to 5 are shown in the table below. The GSP-9300 will automatically detect the signal frequency.

AM/FM Signal Frequency (Hz)					
	Selectable bandwidth of LPF (Hz)				
	<n>=1	<n>=2	<n>=3	<n>=4	<n>=5
≥78,125	156,250	78,125	52,083	39,063	31,250
≥39,063	78,125	39,063	26,042	19,531	15,625
≥19,531	39,063	19,531	13,021	9,766	7,813
≥7,813	15,625	7,813	5,208	3,906	3,125
≥3,906	7,813	3,906	2,604	1,953	1,563
≥1,953	3,906	1,953	1,302	977	781
≥781	1,563	781	521	391	313
≥391	781	391	260	195	156
≥195	391	195	130	98	78
≥78	156	78	52	39	31
≥39	78	39	26	20	16
≥20	39	20	13	10	8
≥8	16	8	5	4	3

Example :DEM:FILT:LPAS B

Set →

→ Query


[[:SENSE]:DEMod:IFBW

Description Sets or queries the IF bandwidth for the AM/FM Analysis function.

Syntax [[:SENSE]:DEMod:IFBW <freq>

Query Syntax [[:SENSE]:DEMod:IFBW?

Parameter	<freq>	<NRf>
Return parameter	<NR3>	Hz
Example	DEM:IFBW 3.0e+5	

[:SENSe]:DEMod:SQUelch:LEVel  

Description	Sets or queries the carrier squelch level.	
Syntax	[:SENSe]:DEMod:SQUelch:LEVel <dBm level>	
Query Syntax	[:SENSe]:DEMod:SQUelch:LEVel?	
Parameter	<dBm level>	<NRf>
Return parameter	<NR3>	Squelch level in dBm
Example	DEM:SQU:LEV 1.30e+2	

[:SENSe]:DETEctor[:FUNctioN]  

Description	Sets or queries the trace detection mode when in manual mode.	
Syntax	[:SENSe]:DETEctor[:FUNctioN] {AVERage SAMPlE POSitive NEGative NORMal}	
Query Syntax	[:SENSe]:DETEctor[:FUNctioN]?	
Parameter/ Return parameter	AVERage	Sets the detector mode to Average.
	SAMPlE	Sets the detector mode to Sample.
	POSitive	Sets the detector mode to Peak+.
	NEGative	Sets the detector mode to Peak-.
	NORMal	Sets the detector mode to Normal.
Example	:DET NORM	

[:SENSe]:DETEctor[:FUNctioN]:AUTO  

Description	Turns the trace detection mode to auto (on) or manual (off) or queries its state.	
Syntax	[:SENSe]:DETEctor[:FUNctioN]:AUTO {OFF ON 0 1}	

Query Syntax	[:SENSe]:DETEctor[:FUNCTION]:AUTO?	
Parameter	0	Turn the detection mode to manual (off).
	1	Turn the detection mode to auto (on).
	OFF	Turn the detection mode to manual (off).
	ON	Turn the detection mode to auto (on).
Return parameter	0	The detection mode is set to manual.
	1	The detection mode is set to automatic.
Example	:DET:AUTO ON	

Set →

[[:SENSe]:EMIFilter:STATe



→ Query

Description	Turns the EMI filter on/off or queries its state.	
Syntax	[:SENSe]:EMIFilter:STATe {OFF ON 0 1}	
Query Syntax	[:SENSe]:EMIFilter:STATe?	
Parameter	0	Turn the EMI filter off.
	1	Turn the EMI filter on.
	OFF	Turn the EMI filter off.
	ON	Turn the EMI filter on.
Return parameter	0	The EMI filter is off.
	1	The EMI filter is on.
Example	:EMI:STAT 0	



**[[:SENSe]:EMIFilter:BANDwidth|BWIDth
[:RESolution]**

Set →



Description	Sets the EMI filter bandwidth (must be set to the exact bandwidth).	
Syntax	[:SENSe]:EMIFilter:BANDwidth BWIDth[:RESolution] <freq>	
Parameter	<freq>	<NRf> (Only 200Hz, 9kHz, 120kHz are valid settings)
Example	:EMIF:BAND 2.0e+2	

[[:SENSe]:FREQuency:CENTer 

Description	Sets or queries the center frequency.	
Syntax	[:SENSe]:FREQuency:CENTer <freq>	
Query Syntax	[:SENSe]:FREQuency:CENTer?	
Parameter	<freq>	<NRf>
Return parameter	<NR3>	Hz
Example	FREQ:CENt 1.0e+9	

[[:SENSe]:FREQuency:CENTer:STEP 

Description	Sets or queries the CF Step frequency.	
Syntax	[:SENSe]:FREQuency:CENTer:STEP <freq>	
Query Syntax	[:SENSe]:FREQuency:CENTer:STEP?	
Parameter	<freq>	<NRf>
Return parameter	<NR3>	Hz
Example	FREQ:CENt:STEP 1.0e+3	

[[:SENSe]:FREQuency:CENTer:STEP:AUTO 

Description	Turns the CF Step frequency setting to auto (on) or manual (off) or queries its state.	
Syntax	[:SENSe]:FREQuency:CENTer:STEP:AUTO {OFF ON 0 1}	
Query Syntax	[:SENSe]:FREQuency:CENTer:STEP:AUTO?	
Parameter	0	Turn CF Step to manual (off).
	1	Turn CF Step to auto (on).
	OFF	Turn CF Step to manual (off).
	ON	Turn CF Step to auto (on).

Return parameter	0	CF Step is set to manual.
	1	CF Step is set to automatic.
Example	:FREQ:CENT:STEP:AUTO OFF	

[[:SENSe]:FREQuency:OFFSet

Set →

→ Query

Description	Sets or queries the frequency offset settings.	
Syntax	[:SENSe]:FREQuency:OFFSet <freq>	
Query Syntax	[:SENSe]:FREQuency:OFFSet?	
Parameter	<freq>	<NRf>
Return parameter	<NR3>	
Example	FREQ:OFFS: 1.0e+6	

[[:SENSe]:FREQuency:SPAN

Set →

→ Query

Description	Sets or queries the span settings.	
Syntax	[:SENSe]:FREQuency:SPAN <freq>	
Query Syntax	[:SENSe]:FREQuency:SPAN?	
Parameter	<freq>	<NRf>
Return parameter	<NR3>	Hz
Example	FREQ:SPAN: 2.0e+9	

[[:SENSe]:FREQuency:SPAN:FULL

Set →

Description	Set the span to Full Span.	
Syntax	[:SENSe]:FREQuency:SPAN:FULL	
Example	:FREQ:SPAN:FULL	



[[:SENSe]:FREQuency:SPAN:PREVious

Set →

Description	Set the span to the previous span setting.	
-------------	--	--

Syntax	[[:SENSe]:FREQuency:SPAN:PREVious
--------	-----------------------------------

Example	:FREQ:SPAN:PREV
---------	-----------------

[[:SENSe]:FREQuency:STARt



Description	Sets or queries the start frequency.
-------------	--------------------------------------

Syntax	[[:SENSe]:FREQuency:STARt <freq>
--------	----------------------------------


Query Syntax	[[:SENSe]:FREQuency:STARt?
--------------	----------------------------

Parameter	<freq>	<NRf>
-----------	--------	-------

Return parameter	<NR3>	Hz
------------------	-------	----

Example	FREQ:STAR: 0
---------	--------------



[[:SENSe]:FREQuency:STOP


Description	Sets or queries the stop frequency.
-------------	-------------------------------------



Syntax	[[:SENSe]:FREQuency:STOP <freq>
--------	---------------------------------

Query Syntax	[[:SENSe]:FREQuency:STOP?
--------------	---------------------------

Parameter	<freq>	<NRf>
-----------	--------	-------

Return parameter	<NR3>	Hz
------------------	-------	----

Example	FREQ:STOP: 1.0e+6
---------	-------------------

**[[:SENSe]:HARMonic:FUNDamental
:FREQuency**



Description	Sets or queries the harmonic frequency.
-------------	---

Syntax	:SENSe:HARMonic:FUNDamental:FREQuency <freq>
--------	--

Query Syntax	:SENSe:HARMonic:FUNDamental:FREQuency?
--------------	--

Parameter	<freq>	<NRf>
-----------	--------	-------

Return parameter	<NR3>	Hz
------------------	-------	----

Example	:SENS:HARM:FUND:FREQ 1.0e+6
---------	-----------------------------

[[:SENSe]:HARMonic:NUMBer (Set) →
→ (Query)

Description	Sets or queries the harmonic number.	
Syntax	:SENSe:HARMonic:NUMBer <NR1>	
Query Syntax	:SENSe:HARMonic:NUMBer?	
Parameter	<NR1>	Harmonic number
Return parameter	<NR1>	Returns the harmonic number
Example	:SENS:HARM:NUMB 3	

[[:SENSe]:LIMit<n>:DELeTe (Set) →

Description	Deletes the chosen limit line.	
Syntax	[:SENSe]:LIMit<n>:DELeTe	
Parameter	<n>	<NR1> limit line number
Example	:LIM3:DEL	

[[:SENSe]:JITTer:OFFSet:STARt (Set) →
→ (Query)

Description	Sets or queries the start offset for phase jitter measurements.	
Syntax	[:SENSe]:JITTer:OFFSet:STARt <freq>	
Query Syntax	[:SENSe]:JITTer:OFFSet:STARt?	
Parameter	<freq>	<NRf>
Return parameter	<NR3>	Hz
Example	JITT:OFFS:STAR 1.0e+7	

[[:SENSe]:JITTer:OFFSet:STOP (Set) →
→ (Query)

Description	Sets or queries the stop offset for phase jitter measurements.	
-------------	--	--

Syntax	[:SENSe]:JITTer:OFFSet:STOP <freq>	
Query Syntax	[:SENSe]:JITTer:OFFSet:STOP?	
Parameter	<freq>	<NRf>
Return parameter	<NR3>	Hz
Example	JITT:OFFS:STOP 1.5e+7	

[:SENSe]:NDB:BANDwidth|BWIDth

Set →

→ Query

Description	Sets or queries the NdB amplitude for NdB bandwidth measurements.	
Syntax	[:SENSe]:NDB:BANDwidth BWIDth <rel_amp>	
Query Syntax	[:SENSe]:NDB:BANDwidth BWIDth?	
Parameter	<rel_amp>	<NRf>
Return parameter	<NR3>	dB
Example	:NDB:BAND 3 dB	

[:SENSe]:OCBW:BANDwidth|BWIDth

Set →

→ Query

Description	Sets or queries the OCBW bandwidth for OCBW measurements.	
Syntax	[:SENSe]:OCBW:BANDwidth BWIDth <freq>	
Query Syntax	[:SENSe]:OCBW:BANDwidth BWIDth?	
Parameter	<freq>	<NRf>
Return parameter	<NR3>	Hz
Example	:OCBW:BAND 4.5+6	

[:SENSe]:OCBW:PERCent

Set →

→ Query

Description	Sets or queries the OCBW percentage (OCBW %) parameter.	
-------------	---	--

Syntax [:SENSe]:OCBW:PERCent <integer>

Query Syntax [:SENSe]:OCBW:PERCent?

Parameter/ Return parameter	<integer>	<NR1>0~100
--------------------------------	-----------	------------

Example :OCBW:PERC 90

[:SENSe]:OCBW:SPACe

Set →
→ Query

Description Sets or queries the OCBW channel space for OCBW measurements.

Syntax [:SENSe]:OCBW:SPACe <freq>

Query Syntax [:SENSe]:OCBW:SPACe?

Parameter	<freq>	<NRf>
-----------	--------	-------

Return parameter	<NR3>
------------------	-------

Example :OCBW:SPAC 6e+7

[:SENSe]:P1DB:AVERAge:COUNT

Set →
→ Query

Description Sets or queries the number of samples used for the average function in the P1dB function.

Syntax :SENSe:P1DB:AVERAge:COUNT <NR1>

Query Syntax :SENSe:P1DB:AVERAge:COUNT?

Parameter	<NR1>	The average number.
-----------	-------	---------------------

Return parameter	<NR1>	Returns the average number.
------------------	-------	-----------------------------

Example :P1DB:AVER:COUN 10

[:SENSe]:P1DB:GAIN:OFFSet

Set →
→ Query

Description Sets or queries the gain offset in dB.

Syntax :SENSe:P1DB:GAIN:OFFSet <rel_ampl>



Query Syntax :SENSe:P1DB:GAIN:OFFSet?

Parameter	<rel_amp>	<NRf>
Return parameter	<NR3>	Returns the gain offset value in dB.
Example	:P1DB:AVER:COUN 10.00e+00	

 →
 → 

[[:SENSE]:PMETER:FREQUENCY

Description	Sets or queries the power meter measurement frequency.	
Syntax	[:SENSE]:PMETER:FREQUENCY <freq>	
Query Syntax	[:SENSE]:PMETER:FREQUENCY?	
Parameter	<freq>	<NRf>
Return parameter	<NR3>	Hz
Example	:PMET:FREQ 2e+7	

 →
 → 

[[:SENSE]:PMETER:HLIMIT

Description	Sets or queries the power meter high limit for pass/fail tests.	
Syntax	[:SENSE]:PMETER:HLIMIT <amp>	
Query Syntax	[:SENSE]:PMETER:HLIMIT?	
Parameter	<amp>	<NRf> power unit, default = dBm
Return parameter	<NR3>	Unit = current unit.
Example	:PMET:HLIM 10	

 →
 → 

[[:SENSE]:PMETER:HOLD:STATE

Description	Turns the power meter Max/Min Hold function on/off or queries its state.	
Syntax	[:SENSE]:PMETER:HOLD:STATE {OFF ON 0 1}	
Query Syntax	[:SENSE]:PMETER:HOLD:STATE?	

Parameter	0	Turn the Max/Min Hold function off.
	1	Turn the Max/Min Hold function on.
	OFF	Turn the Max/Min Hold function off.
	ON	Turn the Max/Min Hold function on.
Return parameter	0	The Max/Min Hold function is off.
	1	The Max/Min Hold function is on.
Example	:PEMT:HOLD:STAT 0	

Set →

[[:SENSe]:PMETer:LLIMit

→ Query

Description	Sets or queries the power meter low limit for pass/fail tests.	
Syntax	[:SENSe]:PMETer:LLIMit <ampl>	
Query Syntax	[:SENSe]:PMETer:LLIMit?	
Parameter	<ampl>	<NRf> power unit, default = dBm
Return parameter	<NR3>	Unit = current unit.
Example	:PMET:LLIM 0	

Set →

[[:SENSe]:PMETer:PSEnSor:MODE

→ Query

Description	Sets or queries the power meter sensor mode.	
Syntax	[:SENSe]:PMETer:PSEnSor:MODE {LOWNoise FASTer}	
Query Syntax	[:SENSe]:PMETer:PSEnSor:MODE?	
Parameter/ Return parameter	LOWNoise	Sets the power meter mode to low noise.
	FASTer	Set the power meter mode to fast.
Example	:PMET:PSEN:MODE	

Set →

[[:SENSe]:PMETer:RECOding:TIME

→ Query

Description	Sets or queries the power meter recording time.	
-------------	---	--

Syntax	[:SENSe]:PMETer:RECORDing:TIME <hour>,<minute>,<second>	
Query Syntax	[:SENSe]:PMETer:RECORDing:TIME?	
Parameter/ Return parameter	<hour> <minute> <second>	<NR1>Recording time: hours. <NR1>Recording time: minutes. <NR1>Recording time: seconds.
Example	:PMET:REC:TIME 1,10,30	

[:SENSe]:PMETer:RECORDing:TIME:STEP

Set →

→ Query

Description	Sets or queries the power meter recording interval in seconds.	
Syntax	[:SENSe]:PMETer:RECORDing:TIME:STEP <time>	
Query Syntax	[:SENSe]:PMETer:RECORDing:TIME:STEP?	
Parameter	<time>	<NRf>
Return parameter	<NR3>	seconds
Example	:PMET:REC:TIME:STEP 10s	

[:SENSe]:POWer[:RF]:GAIN

Set →

→ Query

Description	Sets the preamplifier to Auto or Bypass mode or queries its state.	
Syntax	[:SENSe]:POWer[:RF]:GAIN {AUTO BYPASS}	
Query Syntax	[:SENSe]:POWer[:RF]:GAIN?	
Parameter/ Return parameter	AUTO BYPASS	Sets the preamplifier to auto mode. Sets the preamplifier to bypass mode.
Example	:POW:GAIN AUTO	

**[[:SENSe]:SEMask:BANDwidth|BWIDth:
INTegration**

Set →
→ Query

Description	Sets or queries the channel integration bandwidth for SEM measurements (user defined only).	
Syntax	[:SENSe]:SEMask:BANDwidth BWIDth:INTegration<freq>	
Query Syntax	[:SENSe]:SEMask:BANDwidth BWIDth:INTegration?	
Parameter	<freq>	<NRf>
Return parameter	<NR3>	Hz
Example	:SEM:BAND:INT 3.84e+6	

**[[:SENSe]:SEMask:BANDwidth|BWIDth
[:RESolution]**

Set →
→ Query

Description	Sets or queries the RBW for SEM measurements.	
Syntax	[:SENSe]:SEMask:BANDwidth BWIDth[:RESolution]<freq>	
Query Syntax	[:SENSe]:SEMask:BANDwidth BWIDth[:RESolution]?	
Parameter	<freq>	<NRf>
Return parameter	<NR3>	Hz
Example	:SEM:BAND 2.2e+4	

**[[:SENSe]:SEMask:BANDwidth|BWIDth
[:RESolution]:AUTO**

Set →
→ Query

Description	Turns the RBW setting to auto (on) or manual (off) for SEM measurements or queries its state.	
Syntax	[:SENSe]:SEMask:BANDwidth BWIDth[:RESolution]:AUTO {OFF ON 0 1}	

Query Syntax	[:SENSe]:SEMask:BANDwidth BWIDth[:RESolution]: AUTO?	
Parameter	0	Turn RBW to manual (off).
	1	Turn RBW to auto (on).
	OFF	Turn RBW to manual (off).
	ON	Turn RBW to auto (on).
Return parameter	0	RBW is set to manual.
	1	RBW is set to automatic.
Example	:SEM:BAND: AUTO OFF	

Set →

[:SENSe]:SEMask:CARRier:AUTO

→ Query

Description	Turns the PSDRef or TotalPwrRef modes to auto (on) or manual (off) for SEM measurements or queries their state.	
Syntax	[:SENSe]:SEMask:CARRier:AUTO {OFF ON 0 1}	
Query Syntax	[:SENSe]:SEMask:CARRier:AUTO?	
Parameter	0	Turn PSDRef/TotalPwrRef to manual (off).
	1	Turn PSDRef/TotalPwrRef to auto (on).
	OFF	Turn PSDRef/TotalPwrRef to manual (off).
	ON	Turn PSDRef/TotalPwrRef to auto (on).
Return parameter	0	PSDRef/TotalPwrRef is set to manual.
	1	PSDRef/TotalPwrRef is set to automatic.
Example	:SEM:CARR:AUTO OFF	

Set →

[:SENSe]:SEMask:CARRier:CPSD

→ Query

Description	Sets or queries the value of the PSDRef for SEM measurements.	
Syntax	[:SENSe]:SEMask:CARRier:CPSD <NR3>	
Query Syntax	[:SENSe]:SEMask:CARRier:CPSD?	

Parameter/ Return parameter	<NR3>	PSD ref unit = dBm/Hz
--------------------------------	-------	-----------------------

Example	:SEM:CARR:CPSD 20
---------	-------------------

[[:SENSE]:SEMask:CARRier:POWer

Set →

→ Query

Description	Sets or queries the value of the TotalPwrRef amplitude for SEM measurements.
-------------	--

Syntax	[[:SENSE]:SEMask:CARRier: POWer <ampl>
--------	--

Query Syntax	[[:SENSE]:SEMask:CARRier: POWer?
--------------	----------------------------------

Parameter	<ampl>	<NRf>
-----------	--------	-------

Return parameter	<NR3>	dBm
------------------	-------	-----

Example	:SEM:CARR:POW 2 dbm
---------	---------------------

[[:SENSE]:SEMask:FREQuency:SPAN

Set →

→ Query

Description	Sets or queries the channel span for SEM measurements (user-defined only).
-------------	--

Syntax	[[:SENSE]:SEMask:FREQuency:SPAN<freq>
--------	---------------------------------------

Query Syntax	[[:SENSE]:SEMask:FREQuency:SPAN?
--------------	----------------------------------

Parameter	<freq>	<NR3>
-----------	--------	-------

Return parameter	<NR3>	Hz
------------------	-------	----

Example	:SEM:FREQ:SPAN 2.2e+7
---------	-----------------------

[[:SENSE]:SEMask:GWLan:MODulation

Set →

→ Query

Description	Sets or queries the modulation type for the 802.11g SEM measurement.
-------------	--

Syntax	[[:SENSE]:SEMask:GWLan:MODulation {GRoup<n>}
--------	--

Query Syntax	[[:SENSE]:SEMask:GWLan:MODulation?
--------------	------------------------------------


Parameter/	<n>=1	ERP-DSSS/ERP-PBCC/ERP-CCK
Return parameter	<n>=2	ERP-OFDM/DSSS-OFDM
Example	:SEM:GWL:MOD GR1	

[:SENSe]:SEMask:HELP:STATe Set →
→ Query

Description	Turns the on-screen help window on/off or queries its state.	
Syntax	[:SENSe]:SEMask:HELP:STATe {OFF ON 0 1}	
Query Syntax	[:SENSe]:SEMask:HELP:STATe?	
Parameter	0	Turns the help window off.
	1	Turns the help window on.
	OFF	Turns the help window off.
	ON	Turns the help window on.
Return parameter	0	Help window is off.
	1	Help window is on.
Example	:SEM:HELP:STATE 1	

[:SENSe]:SEMask:NWLan:CHANnel:
 BANDwidth|BWIDth Set →
→ Query

Description	Sets the channel bandwidth for the 802.11n SEM measurement. Only 20MHz or 40MHz can be used.	
Syntax	[:SENSe]:SEMask:NWLan:CHANnel: BANDwidth BWIDth <freq>	
Parameter	<freq>	<NRf> (20 MHz or 40MHz)
Return parameter	<NR3>	
Example	:SEM:NWL:CHAN:BAND 20 MHZ	

[[:SENSe]:SEMask:OFFSet<n>:ADDition:
BANDwidth|BWIDth[:RESolution]? 

Description	Returns the RBW of the selected offset for the additional requirements of the selected 3GPP SEM test.
Query syntax	[[:SENSe]:SEMask:OFFSet<n>:ADDition: BANDwidth BWIDth[:RESolution]?
3GPP-FDD BS Additional Requirements	For operation in bands II, IV, V, X, XII, XIII, XIV and XXV, additional requirements (listed below) apply in addition to the minimum requirements listed above. For 3GPP-FDD UE A means <1> B means <2> (UM P138)

Bands: II, IV, X	Unit: MHz	Additional ^[3]	RBW
	$2.5 \leq A < 3.5$	-15dBm	30kHz
	$3.5 \leq B < \Delta f_{\max}$	-13dBm	1MHz
Bands: V	Unit: MHz	Additional ^[3]	RBW
	$2.5 \leq A < 3.5$	-15dBm	30kHz
	$3.5 \leq B < \Delta f_{\max}$	-13dBm	100kHz
Bands: XII, XIII, XIV	Unit: MHz	Additional ^[3]	RBW
	$2.5 \leq A < 3.5$	-13dBm	30kHz
	$3.5 \leq B < \Delta f_{\max}$	-13dBm	100kHz

3GPP-FDD UE
Additional
Requirements

Additional requirements for 3GPP-FDD UE. For 3GPP-FDD BS:
A means <1>
B means <2>
(UM P137)

Bands II, IV, X	Unit: MHz	Additional ^[3]	RBW
	$2.5 \leq A < 3.5$	-15dBm	30kHz
	$3.5 \leq B < 12.5$	-15dBm	1MHz
Band V	Unit: MHz	Additional ^[3]	RBW
	$2.5 \leq A < 3.5$	-15dBm	30kHz
	$3.5 \leq B < 12.5$	-13dBm	100kHz
Bands XII, XIII, XIV	Unit: MHz	Additional ^[3]	RBW
	$2.5 \leq A < 3.5$	-13dBm	30kHz
	$3.5 \leq B < 12.5$	-13dBm	100kHz

Parameter/ Return parameter	<n>	Offset 1 to 5
	<NR3>	RBW in Hz

Example :SEM:OFFS1:ADD:BAND?
> 3.000000000e+04

[[:SENSE]:SEMask:OFFSet<n>:ADDition:
FREQuency:STARt?

→ Query

Description Returns the start frequency (referred to the center) of the selected offset for the additional requirements of the selected 3GPP SEM test.

Query syntax [[:SENSE]:SEMask:OFFSet<n>:ADDition:
FREQuency:STARt?

Parameter/	<n>	Offset 1 to 5
Return parameter	<NR3>	Start frequency in Hz

Example :SEM:OFFS1:ADD:FREQ:STAR?
>2.5e+6

[[:SENSE]:SEMask:OFFSet<n>:ADDition:
FREQuency:STOP?

→ Query

Description Returns the stop frequency (referred to the center) of the selected offset for the additional requirements of the selected 3GPP SEM test.

Query syntax [[:SENSE]:SEMask:OFFSet<n>:ADDition:
FREQuency:STOP?

Parameter/	<n>	Offset 1 to 5
Return parameter	<NR3>	Stop frequency in Hz

Example :SEM:OFFS1:ADD:FREQ:STOP?
>3.5e+6

[[:SENSe]:SEMask:OFFSet<n>:ADDition:
STARt:ABSolute?

→ Query

Description	Returns the “start” amplitude (dBm) of the Absolute Mask for the selected offset for the additional requirements of the selected 3GPP SEM test.	
Query syntax	[:SENSe]:SEMask:OFFSet<n>:ADDition:STARt:ABSolute?	
Parameter/ Return parameter	<n> <NR3>	Offset 1 to 5 Amplitude at start frequency
Example	:SEM:OFFS1:ADD:STAR:ABS? >-1.5e+1	

[[:SENSe]:SEMask:OFFSet<n>:ADDition:
STOP:ABSolute?

→ Query

Description	Returns the “Stop” amplitude (dBm) of the Absolute Mask for the selected offset for the additional requirements of the selected 3GPP SEM test.	
Query syntax	[:SENSe]:SEMask:OFFSet<n>:ADDition:STOP:ABSolute?	
Parameter/ Return parameter	<n> <NR3>	Offset 1 to 5 Amplitude at stop frequency
Example	:SEM:OFFS1:ADD:STOP:ABS? >-1.5e+1	



[[:SENSe]:SEMask:OFFSet<n>:BANDwidth|
BWIDth[:RESolution]

Set →



→ Query

Description	Sets or queries the resolution bandwidth of the selected offset.
-------------	--

Syntax	[:SENSe]:SEMask:OFFSet<n>:BANDwidth BWIDth[:RESolution] <freq>	
Query Syntax	[:SENSe]:SEMask:OFFSet<n>:BANDwidth BWIDth[:RESolution]?	
Parameter/ Return parameter	<freq> <n>	<NR3> Hz <NR1>offset 1~5
Example	SEM:OFFS1:BAND 3.0e+3	



[:SENSe]:SEMask:OFFSet<n>:BANDwidth|B  →
 Width[:RESolution]:AUTO 

Description	Turns the resolution bandwidth for the selected channel to manual or automatic mode or queries its state.	
Syntax	[:SENSe]:SEMask:OFFSet<n>:BANDwidth BWIDth[:RESolution]:AUTO {OFF ON 0 1}	
Query Syntax	[:SENSe]:SEMask:OFFSet<n>:BANDwidth BWIDth[:RESolution]:AUTO?	
Parameter	0 1 OFF ON	Set RBW to manual. Set RBW to auto. Set RBW to manual. Set RBW to auto.
Return parameter	0 1	RBW is set to manual. RBW is set to auto.



[:SENSe]:SEMask:OFFSet<n>:FREQuency:  →
 START 

Description	Sets or queries the start frequency of the selected offset.	
Syntax	[:SENSe]:SEMask:OFFSet<n>:FREQuency:START<freq>	
Query Syntax	[:SENSe]:SEMask:OFFSet<n>:FREQuency:START?	



Parameter/	<freq>	<NR3> Hz
Return parameter	<n>	<NR1>offset 1~5
Example	SEM:OFFS1:FREQ:STAR 2.5e+3	

[:SENSe]:SEMask:OFFSet<n>:FREQuency:  STOP 

Description	Sets or queries the stop frequency of the selected offset.	
Syntax	[:SENSe]:SEMask:OFFSet<n>:FREQuency:STOP <freq>	
Query Syntax	[:SENSe]:SEMask:OFFSet<n>:FREQuency:STOP?	
Parameter/	<freq>	<NR3> Hz
Return parameter	<n>	<NR1>offset 1~5
Example	SEM:OFFS1:FREQ:STOP 2.5e+3	



[:SENSe]:SEMask:OFFSet<n>:STARt:  ABSolute 

Description	Sets or queries the amplitude of the start frequency of the Absolute Mask for the selected offset.	
Syntax	[:SENSe]:SEMask:OFFSet<n>:STARt:ABSolute <ampl>	
Query Syntax	[:SENSe]:SEMask:OFFSet<n>:STARt:ABSolute?	
Parameter/	<ampl>	<NR3> dBm
Return parameter	<n>	<NR1>offset 1~5
Example	SEM:OFFS1:STAR:ABS 1.5e+1	



[:SENSe]:SEMask:OFFSet<n>:STARt:  RELative 

Description	Sets or queries the amplitude of the start frequency of the Relative Mask for the selected offset.	
-------------	--	--

Syntax	[:SENSe]:SEMask:OFFSet<n>:STARt:RELative <ampl>	
Query Syntax	[:SENSe]:SEMask:OFFSet<n>:STARt:RELative?	
Parameter/ Return parameter	<ampl> <n>	<NR3> dBc <NR1> offset 1~5
Example	SEM:OFFS1:STAR:REL 2.5e+1	

[:SENSe]:SEMask:OFFSet<n>:STATe  

Description	Turns the selected offset on/off or queries its state.	
Syntax	[:SENSe]:SEMask:OFFSet<n>:STATe {OFF ON 0 1}	
Query Syntax	[:SENSe]:SEMask:OFFSet<n>:STATe?	
Parameter	0 1 OFF ON	Turns the selected offset off. Turns the selected offset on. Turns the selected offset off. Turns the selected offset on.
Return parameter	0 1	The selected offset is off. The selected offset is on.
Example	SEM:OFFS1:STAT 1	

[:SENSe]:SEMask:OFFSet<n>:STOP
:ABSolute  

Description	Sets or queries the amplitude of the stop frequency of the Absolute Mask for the selected offset.	
Syntax	[:SENSe]:SEMask:OFFSet<n>:STOP:ABSolute <ampl>	
Query Syntax	[:SENSe]:SEMask:OFFSet<n>:STOP:ABSolute?	
Parameter/ Return parameter	<ampl> <n>	<NR3> dBm <NR1>offset 1~5
Example	SEM:OFFS1:STOP:ABS 1.5e+1	

[[:SENSe]:SEMask:OFFSet<n>:STOP:
ABSolute:COUPle

Set →
→ Query

Description	Couples the Absolute Stop amplitude to the Absolute Start amplitude for the selected offset.	
Syntax	[:SENSe]:SEMask:OFFSet<n>:STOP:ABSolute:COUPle {OFF ON 0 1}	
Query Syntax	[:SENSe]:SEMask:OFFSet<n>:STOP:ABSolute:COUPle?	
Parameter	0 1 OFF ON	Turns coupling off. Turns coupling on. Turns coupling off. Turns coupling on.
Return parameter	0 1	Coupling is off. Coupling is on.
Example	SEM:OFFS1:STOP:ABS:COUP 0	

[[:SENSe]:SEMask:OFFSet<n>:STOP:
RELative

Set →
→ Query

Description	Sets or queries the amplitude of the stop frequency of the Relative Mask for the selected offset.	
Syntax	[:SENSe]:SEMask:OFFSet<n>:STOP:RELative <ampl>	
Query Syntax	[:SENSe]:SEMask:OFFSet<n>:STOP:RELative?	
Parameter/ Return parameter	<ampl> <n>	<NR3> dBc <NR1> offset 1~5
Example	SEM:OFFS1:STOP:REL 1.5e+1	

**[[:SENSE]:SEMask:OFFSet<n>:STOP:
RELative:COUPLE**

Set →
→ **Query**

Description	Couples the Relative Stop amplitude to the Relative Start amplitude for the selected offset.	
Syntax	[:SENSE]:SEMask:OFFSet<n>:STOP:RELative:COUPLE {OFF ON 0 1}	
Query Syntax	[:SENSE]:SEMask:OFFSet<n>:STOP:RELative:COUPLE?	
Parameter	0	Turns coupling off.
	1	Turns coupling on.
	OFF	Turns coupling off.
	ON	Turns coupling on.
Return parameter	0	Coupling is off.
	1	Coupling is on.

[[:SENSE]:SEMask:OFFSet<n>:TEST

Set →
→ **Query**

Description	Sets or queries the masks to use for the Fail Mask(s).	
Syntax	[:SENSE]:SEMask:OFFSet<n>:TEST {ABS REL AND OR}	
Query Syntax	[:SENSE]:SEMask:OFFSet<n>:TEST?	
Parameter/ Return parameter	ABS	Absolute mask
	REL	Relative mask
	AND	Absolute and Relative mask
	OR	Absolute or Relative mask
Example	:SEM:OFFS:1:TEST ABS	

[[:SENSE]:SEMask:SElect

Set →
→ **Query**

Description	Selects or queries the type of spectrum emission mask.
-------------	--

Syntax	[:SENSe]:SEMask:SElect {MANual W3GPP BWLan GWLan NWLan WIMax}	
Query Syntax	[:SENSe]:SEMask:SElect?	
Parameter/ Return parameter	MANual	User-defined SEM
	W3GPP	3GPP SEM
	BWLan	802.11b SEM
	GWLan	802.11g SEM
	NWLan	802.11n SEM
	WIMax	802.16 SEM
Example	:SEM:SEL MAN	

[:SENSe]:SEMask:TYPE

Set →

→ Query

Description	Selects or queries the method used as the reference for calculating the offset power: Total power reference or power spectral density reference.	
Syntax	[:SENSe]:SEMask:TYPE {PSDRef TPRef}	
Query Syntax	[:SENSe]:SEMask:TYPE?	
Parameter/ Return parameter	PSDRef	Power Spectral Density Reference
	TPRef	Total Power Reference
Example	:SEM:TYPE PSDR	

[:SENSe]:SEMask:W3GPP:DUPLex:TYPE

Set →

→ Query

Description	Selects or queries the type of duplexing used for 3GPP tests.	
Syntax	[:SENSe]:SEMask:W3GPP:DUPLex:TYPE {FDD TDD}	
Query Syntax	[:SENSe]:SEMask:W3GPP:DUPLex:TYPE?	
Parameter/ Return parameter	FDD	Frequency-division duplexing
	TDD	Time-division duplexing
Example	:SEM:W3GPP:DUPL:TYPE FDD	

[:SENSe]:SEMask:W3GPP:FDD:ADDITION: LIMit (Set) →
→ (Query)

Description	Selects or queries the operating band used for the 3GPP FDD additional requirements. See the user manual for a list of the 3GPP operation bands.	
Syntax	[:SENSe]:SEMask:W3GPP:FDD:ADDITION:LIMit {NONE BAND<n>}	
Query Syntax	[:SENSe]:SEMask:W3GPP:FDD:ADDITION:LIMit?	
Parameter/ Return parameter	NONE BAND<n>	When n = band number
Example	:SEM:W3GPP:FDD:ADD:LIM BAND4	

[:SENSe]:SEMask:W3GPP:FDD:ADDITION: MOPower (Set) →
→ (Query)

Description	Selects or queries Max Out Power for the 3GPP additional requirements for the selected offset. Please see the user manual for a list of the selectable maximum power output levels.	
Syntax	[:SENSe]:SEMask:W3GPP:FDD:ADDITION:MOPower {NONE LEVEL<n>}	
Query Syntax	[:SENSe]:SEMask:W3GPP:FDD:ADDITION:MOPower?	
Parameter/ Return parameter	NONE LEVEL<n>	n=1 for 6≤P≤20 n=2 for P<6
Example	:SEM:W3GPP:FDD:ADD:MOP LEV1	

[:SENSe]:SEMask:W3GPP:FDD:MOPower (Set) →
→ (Query)

Description	Selects or queries Max Out Power for the selected offset. Please see the user manual for a list of the selectable maximum power output levels.	
-------------	--	--

Syntax	[:SENSe]:SEMask:W3GPP:FDD:MOPower {LEVel<n>}	
Query Syntax	[:SENSe]:SEMask:W3GPP:FDD:MOPower?	
Parameter/ Return parameter	NONE LEVEL<n>	n=1 for 43<=P n=2 for 39<=P<43 n=3 for 31<=P<39 n=4 for P<31
Example	:SEM:W3GPP:FDD:MOP LEV1	

[:SENSe]:SEMask:W3GPP:FDD:TRANsmit:  
MODE

Description	Selects or queries the transmit mode of the FDD 3GPP test: Base station, or User Equipment.	
Syntax	[:SENSe]:SEMask:W3GPP:FDD:TRANsmit:MODE {BS UE}	
Query Syntax	[:SENSe]:SEMask:W3GPP:FDD:TRANsmit:MODE?	
Parameter/ Return parameter	BS UE	Base station User Equipment
Example	:SEM:W3GPP:FDD:TRAN:MODE UE	

 
[:SENSe]:SEMask:W3GPP:TDD:CHIP:RATE

Description	Selects or queries the chip rate for TDD 3GPP tests.	
Syntax	[:SENSe]:SEMask:W3GPP:TDD:CHIP:RATE {3.84e+6 1.28e+6 7.68e+6}	
Query Syntax	[:SENSe]:SEMask:W3GPP:TDD:CHIP:RATE?	
Parameter/ Return parameter	3.84e+6 1.28e+6 7.68e+6	<freq> <freq> <freq>
Example	:SEM:W3GPP:TDD:CHIP:RATE 3.84e+6	

[[:SENSe]:SEMask:W3GPP:TDD:MOPower (Set) →
→ (Query)

Description	Selects or queries Max Out Power for TDD 3GPP tests. See the user manual for a list of the power levels.	
Syntax	[:SENSe]:SEMask:W3GPP:TDD:MOPower {LEVEL<n>}	
Query Syntax	[:SENSe]:SEMask:W3GPP:TDD:MOPower?	
Parameter/ Return parameter	LEVEL<n>	For 3GPP TDD BS 3.84 and 7.68Mcps : n=1 for 43<=P n=2 for 39<=P<43 n=3 for 31<=P<39 n=4 for P<31 for 3GPP TDD BS 1.28Mcps: n=1 for 34<=P n=2 for 26<=P<34 n=3 for 26<31
Example	:SEM:W3GPP:TDD:MOP LEV1	

[[:SENSe]:SEMask:W3GPP:TDD:TRANsmit:MODE (Set) →
→ (Query)

Description	Selects or queries the transmit mode of the TDD 3GPP test: Base station, or User Equipment.	
Syntax	[:SENSe]:SEMask:W3GPP:TDD:TRANsmit:MODE {BS UE}	
Query Syntax	[:SENSe]:SEMask:W3GPP:TDD:TRANsmit:MODE?	
Parameter/ Return parameter	BS UE	Base station User Equipment
Example	:SEM:W3GPP:TDD:TRAN:MODE UE	

```
[[:SENSe]:SEMask:WIMax:CHANnel:
BANDwidth|BWIDth
```

Set →
→ Query

Description Selects or queries the 802.16 channel bandwidth (10M or 20M channelization).

Syntax [:SENSe]:SEMask:WIMax:CHANnel:BANDwidth|BWIDth {1e+7|2e+7}

Query Syntax [:SENSe]:SEMask:WIMax:CHANnel:BANDwidth|BWIDth?

Parameter/	1e+7	<freq>
Return parameter	2e+7	<freq>

Example :SEM:WIM:CHAN:BAND 1e+7

```
[[:SENSe]:SEQuence<n>:DELeTe
```

Set →

Description Deletes the chosen sequence.

Syntax [:SENSe]:SEQuence<n>:DELeTe

Parameter	<n>	<NR1> sequence 1 to 5.
-----------	-----	------------------------

Example :SEQ1:DEL

```
[[:SENSe]:SWEep:EGATe:DELaY
```

Set →
→ Query

Description Sets or queries the gate delay time.

Syntax [:SENSe]:SWEep:EGATe:DELaY <time>

Query Syntax [:SENSe]:SWEep:EGATe:DELaY?

Parameter/	<time>	Gate delay time in seconds
Return parameter		

Example SWE:EGAT:DEL 10 ms




[[:SENSe]:SWEep:EGATe:LENGth

Description	Sets or queries the gate length time.	
Syntax	[:SENSe]:SWEep:EGATe:LENGth <time>	
Query Syntax	[:SENSe]:SWEep:EGATe:LENGth?	
Parameter/ Return parameter	<time>	Gate length time in seconds
Example	SWE:EGAT:LENG 10 ms	




[[:SENSe]:SWEep:EGATe:STATe

Description	Turns the gated sweep mode on/off or queries its state.	
Syntax	[:SENSe]:SWEep:EGATe:STATe {OFF ON 0 1}	
Query Syntax	[:SENSe]:SWEep:EGATe:STATe?	
Parameter	0 1 OFF ON	Turns gated sweep mode off. Turns gated sweep mode on. Turns gated sweep mode off. Turns gated sweep mode on.
Return parameter	0 1	Gated sweep mode is off. Gated sweep mode is on.
Example	:SWE:EGAT:STAT 1	




[[:SENSe]:SWEep:MODE

Description	Sets or queries the sweep mode.	
Syntax	:SENSe:SWEep:MODE {FAST NORMAL}	
Query Syntax	:SENSe:SWEep:MODE?	
Parameter	FAST NORMAL	Sets to fast mode Sets to normal mode

Return parameter	FAST	Sets to fast mode
	NORMAL	Sets to normal mode

Example :SENS:SWE:MODE FAST

[[:SENSe]:SWEep:TIME

Set →

→ Query

Description Sets the sweep time.

Syntax [:SENSe]:SWEep:TIME <time>

Query Syntax [:SENSe]:SWEep:TIME?

Parameter/ Return parameter	<time>	Sweep time in seconds
--------------------------------	--------	-----------------------

Example SWE:TIME 60 ms

Set →

[[:SENSe]:SWEep:TIME:AUTO

→ Query

Description Turns the Sweep time setting to auto (on) or manual (off).

Syntax [:SENSe]:SWEep:TIME:AUTO {OFF|ON|0|1}

Query Syntax [:SENSe]:SWEep:TIME:AUTO?

Parameter	0	Turn sweep time to manual (off).
	1	Turn sweep time to auto (on).
	OFF	Turn sweep time to manual (off).
	ON	Turn sweep time to auto (on).

Return parameter	0	Sweep time is set to manual.
	1	Sweep time is set to automatic.

Example :SWE:TIME:AUTO 0

Set →

[[:SENSe]:TOI:REFeRence

→ Query

Description Sets or queries the TOI reference to the upper or lower base.

Syntax [:SENSe]:TOI:REFeRence {UPPeR|LOWeR}

Query Syntax [:SENSe]:TOI:REFeRence?

Parameter/UPPer Upper base.

Return parameter LOWer Lower base.

Example :TOI:REF UPP

Set →

[:SENSe]:TOI:LIMit

→ Query

Description Sets the TOI pass/fail limit amplitude.

Syntax [:SENSe]:TOI:LIMit <ampl>

Query Syntax [:SENSe]:TOI:LIMit?

Parameter <ampl> <NRf>Power or voltage

Return parameter <NR3>

Example TOI:LIM 30

SOURce Commands

:SOURce:POWer[:LEVel][:IMMediate][:AMPLitude] .. 191

:SOURce:POWer[:LEVel][:IMMediate][:AMPLitude]

:OFFSet..... 191

:SOURce:POWer[:LEVel][:IMMediate][:AMPLitude]



:STEP 192

:SOURce:POWer[:LEVel][:IMMediate][:AMPLitude]:

STEP:AUTO 192



:SOURce:POWer:MODE 193

:SOURce:POWer:SWEEp..... 193

:SOURce:POWer[:LEVel][:IMMediate]  

[:AMPLitude]

Description	Sets or queries the tracking generator power level.	
Syntax	:SOURce:POWer[:LEVel][:IMMediate][:AMPLitude] <ampl>	
Query Syntax	:SOURce:POWer[:LEVel][:IMMediate][:AMPLitude]?	
Parameter	<ampl>	<NRf>Power or voltage
Return parameter	<NR3>	
Example	:SOUR:POW 30 dbm	


:SOURce:POWer[:LEVel][:IMMediate]  

[:AMPLitude]:OFFSet

Description	Sets or queries the tracking generator offset level.	
Syntax	:SOURce:POWer[:LEVel][:IMMediate][:AMPLitude] :OFFSet <rel_ampl>	
Query Syntax	:SOURce:POWer[:LEVel][:IMMediate][:AMPLitude] :OFFSet?	


Parameter	<rel_ampl>	<NRf>
Return parameter	<NR3>	dB
Example	:SOUR:POW:OFFS 10 db	

:SOURce:POWer[:LEVel][:IMMediate]
[:AMPLitude]:STEP



Description	Sets or queries the tracking generator step level.	
Syntax	:SOURce:POWer[:LEVel][:IMMediate][:AMPLitude]:STEP <rel_ampl>	
Query Syntax	:SOURce:POWer[:LEVel][:IMMediate][:AMPLitude]:STEP?	
Parameter	<rel_ampl>	<NRf>
Return parameter	<NR3>	dB
Example	:SOUR:POW:STEP .5 db	

:SOURce:POWer[:LEVel][:IMMediate]
[:AMPLitude]:STEP:AUTO



Description	Turns the tracking generator step level setting to auto (on) or manual (off).	
Syntax	:SOURce:POWer[:LEVel][:IMMediate][:AMPLitude]:STEP:AUTO {OFF ON 0 1}	
Query Syntax	:SOURce:POWer[:LEVel][:IMMediate][:AMPLitude]:STEP:AUTO?	
Parameter	0	Turn TG step level to manual (off).
	1	Turn TG step level to auto (on).
	OFF	Turn TG step level to manual (off).
	ON	Turn TG step level to auto (on).
Return parameter	0	TG step level is set to manual.
	1	TG step level is set to automatic.
Example	:SOUR:POW:STEP:AUTO 1	

:SOURce:POWer:MODE

Set

→

→

Query

Description	Sets the Power Sweep mode.	
Syntax	:SOURce:POWer:MODE {FIXed SWEEp}	
Query Syntax	:SOURce:POWer:MODE?	
Parameter/ Return parameter	FIXed SWEEp	Power sweep off. Power sweep on.
Example	:SOUR:POW:MODE FIX	

:SOURce:POWer:SWEEp

Set

→

→

Query

Description	Sets the Power Sweep offset level.	
Syntax	:SOURce:POWer:SWEEp <rel_ampl>	
Query Syntax	:SOURce:POWer:SWEEp?	
Parameter	<rel_ampl>	<NRf> (-5 to +5 dB)
Return parameter	<NR3>	dB
Example	:SOUR:POW:SWE 5 db	

SYSTem Commands

:SYSTem:ALARm:STATe.....	194
:SYSTem:CLOCK<n>:DATE.....	195
:SYSTem:CLOCK<n>:MODE	195
:SYSTem:CLOCK<n>:STATe	196
:SYSTem:CLOCK<n>:TIME	196
:SYSTem:COMMunicate:GPIB[:SELF]:ADDReSS	196
:SYSTem:COMMunicate:LANReSet	197
:SYSTem:COMMunicate:SERIal[:RECeive]:BAUD.....	197
:SYSTem:COMMunicate:USB:MODE	197
:SYSTem:DATE	197
:SYSTem:ERRor:CLEar	198
:SYSTem:ERRor[:NEXT]?.....	198
:SYSTem:KLOCK.....	198
:SYSTem:PRESet.....	198
:SYSTem:PRESet:TYPE	199
:SYSTem:PRESet:USER:SAVE	199
:SYSTem:REBoot.....	199
:SYSTem:SHUTdown.....	199
:SYSTem:TIME	199
:SYSTem:UPDate	200
:SYSTem:VERSIon:HARDware?	200
:SYSTem:VERSIon:SOFTware?.....	200

Set

→

→

Query

:SYSTem:ALARm:STATe

Description	Sets the system alarm output on/off.	
Syntax	:SYSTem:ALARm:STATe {OFF ON 0 1}	
Query Syntax	:SYSTem:ALARm:STATe?	
Parameter	0	Turn the alarm off.
	1	Turn the alarm on.
	OFF	Turn the alarm off.
	ON	Turn the alarm on.
Return parameter	0	The alarm is off.
	1	The alarm is on.

Example :SYST:ALAR:STAT 1

:SYSTem:CLOCK<n>:DATE

Set →

→ Query

Description Sets the day for the selected wake-up clock.

Syntax :SYSTem:CLOCK<n>:DATE
[MONday|TUESday|WEDnesday|THURsday|FRIday|SATurday|SUNday]

Query Syntax :SYSTem:CLOCK<n>:DATE?

Parameter/ Return parameter	<n>	Wake-up clock number 1 to 7
	MONday	Set to Monday
	TUESday	Set to Tuesday
	WEDnesday	Set to Wednesday
	THURsday	Set to Thursday
	FRIday	Set to Friday
	SATurday	Set to Saturday
	SUNday	Set to Sunday

Example :SYST:CLOC1:DATE MON

:SYSTem:CLOCK<n>:MODE

Set →

→ Query

Description Sets the alarm mode for the selected wake-up clock.

Syntax :SYSTem:CLOCK<n>:MODE {REPeat|SINGle}

Query Syntax :SYSTem:CLOCK<n>:MODE?

Parameter/ Return parameter	<n>	Wake-up clock number 1 to 7
	REPeat	Set the wake-up clock to repeat.
	SINGle	Set the wake-up clock to single.

Example :SYST:CLOC1:MODE REP

:SYSTem:CLOCK<n>:STATe

Set →

→ Query

Description	Turns the selected wake-up clock on/off.	
Syntax	:SYSTem:CLOCK<n>:STATe {OFF ON 0 1}	
Query Syntax	:SYSTem:CLOCK<n>:STATe?	
Parameter	<n>	Wake-up clock number 1 to 7
	0	Turn the wake-up clock off.
	1	Turn the wake-up clock on.
	OFF	Turn the wake-up clock off.
	ON	Turn the wake-up clock off.
Return parameter	0	The wake-up clock is off.
	1	The wake-up clock is on.
Example	:SYST:CLOC1:STATE 1	

:SYSTem:CLOCK<n>:TIME

Set →

→ Query

Description	Sets the alarm time for the selected wake-up clock.	
Syntax	:SYSTem:CLOCK<n>:TIME <hour>,<minute>	
Query Syntax	:SYSTem:CLOCK<n>:TIME?	
Parameter/ Return parameter	<hour>	<NR1> Sets the alarm hour.
	<minute>	<NR1> Sets the alarm minute.
	<n>	Wake-up clock number 1 to 7
Example	:SYST:CLOC1:TIME 20,50	

:SYSTem:COMMunicate:GPIB[:SELF]

:ADDRes

Set →

Description	Sets the GPIB address.	
Syntax	:SYSTem:COMMunicate:GPIB[:SELF]:ADDRes <integer>	

Parameter	<integer>	0 to 30
-----------	-----------	---------

Example	:SYST:COMM:GPIB:ADDR 10
---------	-------------------------

:SYSTem:COMMunicate:LANReset



Description	Reset the LAN configuration and reboot.
-------------	---

Syntax	:SYSTem:COMMunicate:LANReset
--------	------------------------------

Example	:SYST:COMM:LANR
---------	-----------------

:SYSTem:COMMunicate:SERial[:RECeive]

:BAUD



Description	Sets the RS232 Baud rate.
-------------	---------------------------

Syntax	:SYSTem: COMMunicate:SERial[:RECeive]:BAUD <integer>
--------	---

Parameter	<integer>	300 600 1200 2400 4800 9600 19200 38400 57600 115200
-----------	-----------	--

Example	:SYST:COMM:SER:BAUD 9600
---------	--------------------------

:SYSTem:COMMunicate:USB:MODE




Description	Configures the USB mode.
-------------	--------------------------


Syntax	:SYSTem:COMMunicate:USB:MODE {HOST DEVICE}
--------	--

Parameter/ Return parameter	HOST	USB host mode
	DEVIce	USB device mode

Example	:SYST:COMM:USB:MODE DEV
---------	-------------------------



:SYSTem:DATE



Description	Sets the system date.
-------------	-----------------------

Syntax	:SYSTem:DATE <year>,<month>,<day>
--------	-----------------------------------

Query Syntax	:SYSTem:DATE?	
Parameter/	<year>	<NR1>
Return parameter	<month>	<NR1>
	<day>	<NR1>
Example	:SYST:DATE 2011,03,27	

:SYSTem:ERRor:CLEar (Set) →

Description	Clears the error messages from the error queue.
Syntax	:SYSTem:ERRor:CLEar

:SYSTem:ERRor[:NEXT]? → (Query)

Description	Returns the next message from the error queue. Reading the error from the error queue will clear that error from the queue.
Syntax	:SYST:ERR?

:SYSTem:KLOCK (Set) →

Description	Locks/unlocks the front panel keys.	
Syntax	:SYSTem:KLOCK {ON OFF}	
Parameter	ON	Lock the front panel keys
	OFF	Unlock the front panel keys
Example	:SYST:KLOCK OFF	

:SYSTem:PRESet (Set) →

Description	Returns the GSP-9300 to preset settings.
Syntax	:SYST:PRES

:SYSTem:PRESet:TYPE (Set) →
→ (Query)

Description	Sets the preset type between user-defined and factory default.	
Syntax	:SYSTem:PRESet:TYPE {USER FACTory}	
Query Syntax	:SYSTem:PRESet:TYPE?	
Parameter/ Return parameter	USER FACTory	User defined preset Factory default
Example	:SYST:PRES:TYPE USER	

:SYSTem:PRESet:USER:SAVE (Set) →

Description	Save the current environment as the “User” preset settings.
Syntax	:SYST:PRES:USER:SAVE

:SYSTem:REBoot (Set) →

Description	Restart/Reboot the GSP-9300.
Syntax	:SYSTem:REBoot

:SYSTem:SHUTdown (Set) →

Description	Shut down the GSP-9300.
Syntax	:SYST:SHUT

:SYSTem:TIME (Set) →
→ (Query)

Description	Sets the system time.
Syntax	:SYSTem:TIME <hour>,<minute>,<second>
Query Syntax	:SYSTem:TIME?

Parameter/	<hour>	<NR1>
Return parameter	<minute>	<NR1>
	<second>	<NR1>
Example	:SYST:TIME 19,26,30	

:SYSTem:UPDate

Set →

Description	Updates the system with new firmware from files located on an external USB drive. The firmware files must be included in the directory named /gsp931.
Warning	Do not perform this command if the update file is <i>not</i> on the USB drive. If the update file is not on the USB drive, it will cause the instrument to continuously loop until a USB drive with the appropriate update file is inserted into the USB drive.
Syntax	:SYST:UPD

:SYSTem:VERsion:HARDware?

→ Query

Description	Returns the system firmware version.
Query Syntax	:SYSTem:VERsion:HARDware?
Return parameter	<string> T.X.X.X.X
Example	:SYST:VERs:HARD? >T.1.0.0.0

:SYSTem:VERsion:SOFTware?

→ Query

Description	Returns the system software version.
Query Syntax	:SYSTem:VERsion:SOFTware?

Return parameter	<string>	T1.00_2014.05.28_22 Where: T1.00 = firmware version 2014 = year 05 = month 28 = day 22 = internal reference (not for end-user)
Example	:SYST:VERS:SOFT? > T1.00_2014.05.28_22\n	

STATus Commands

:STATus:OPERation:CONDition?	202
:STATus:OPERation:ENABle	203
:STATus:OPERation[:EVENT]?	203
:STATus:OPERation:NTRansition	204
:STATus:OPERation:PTRansition	204
:STATus:QUEStionable:CONDition?	205
:STATus:QUEStionable:ENABle	205
:STATus:QUEStionable[:EVENT]?	206
:STATus:QUEStionable:NTRansition	206
:STATus:QUEStionable:PTRansition	207
:STATus:QUEStionable:FREQuency:CONDition?	207
:STATus:QUEStionable:FREQuency:ENABle	208
:STATus:QUEStionable:FREQuency[:EVENT]?	208
:STATus:QUEStionable:FREQuency:NTRansition	208
:STATus:QUEStionable:FREQuency:PTRansition	209
:STATus:QUEStionable:ACPLimit:CONDition?	209
:STATus:QUEStionable:ACPLimit:ENABle	210
:STATus:QUEStionable:ACPLimit[:EVENT]?	210
:STATus:QUEStionable:ACPLimit:NTRansition	211
:STATus:QUEStionable:ACPLimit:PTRansition	211
:STATus:QUEStionable:SEMLimit :CONDition?	212
:STATus:QUEStionable:SEMLimit:ENABle?	213
:STATus:QUEStionable:SEMLimit[:EVENT]?	213
:STATus:QUEStionable:SEMLimit :NTRansition	214
:STATus:QUEStionable:SEMLimit:PTRansition	215
:STATus:QUEStionable:TOILimit:CONDition?	215
:STATus:QUEStionable:TOILimit:ENABle	216
:STATus:QUEStionable:TOILimit[:EVENT]?	216
:STATus:QUEStionable:TOILimit:NTRansition	216
:STATus:QUEStionable:TOILimit:PTRansition	217
:STATus:PRESet	217

:STATus:OPERation:CONDition?



Description	Returns the bit weight of the Operation Status Condition register.
-------------	--

Query Syntax	:STATus:OPERation:CONDition?
--------------	------------------------------

Return parameter	Bit	Bit Weight	Description
	0~2	N/A	Not used
	3	8	Sweeping
	4	16	Measuring
	5	32	Wait for Trigger
	6~15	N/A	Not used
Example	:STAT:OPER:COND? >8		

:STATus:OPERation:ENABLE  


Description Sets or queries the Operation Status Event Enable register.

Syntax :STATus:OPERation:ENABLE <integer>

Query Syntax :STATus:OPERation:ENABLE?

Return parameter	Bit	Bit Weight	Description
	0~2	N/A	Not used
	3	8	Sweeping
	4	16	Measuring
	5	32	Wait for Trigger
	6~15	N/A	Not used

Example :STAT:OPER:ENAB 32

:STATus:OPERation[:EVENT]? 

Description Returns the bit weight of the Operation Status Event register. Reading this register will clear the event register.

Query Syntax :STATus:OPERation[:EVENT]?

Return parameter	Bit	Bit Weight	Description
	0~2	N/A	Not used
	3	8	Sweeping
	4	16	Measuring
	5	32	Wait for Trigger
	6~15	N/A	Not used

Example :STAT:OPER?
>8

Set →

→ Query

:STATus:OPERation:NTRansition

Description Sets or queries the bit weight of the NTR filter for the Operation Status register.

Syntax :STATus:OPERation:NTRansition <integer>

Query Syntax :STATus:OPERation:NTRansition?

Return parameter	Bit	Bit Weight	Description
	0~2	N/A	Not used
	3	8	Sweeping
	4	16	Measuring
	5	32	Wait for Trigger
	6~15	N/A	Not used

Example :STAT:OPER:NTR 32

Set →

→ Query

:STATus:OPERation:PTRansition

Description Sets or queries the bit weight of the PTR filter for the Operation Status register.

Syntax :STATus:OPERation:PTRansition <integer>

Query Syntax :STATus:OPERation:PTRansition?

Return parameter	Bit	Bit Weight	Description
	0~2	N/A	Not used
	3	8	Sweeping
	4	16	Measuring
	5	32	Wait for Trigger
	6~15	N/A	Not used
Example	:STAT:OPER:PTR 32		

:STATus:QUEStionable:CONDition?

→ Query

Description Returns the bit weight of the Questionable Status Condition register.

Query Syntax :STATus:QUEStionable:CONDition?

Return parameter	Bit	Bit Weight	Description
	5	32	Frequency
	8	256	Uncal
	9	512	Limit Fail
	10	1024	ACPLimit
	11	2048	SEM Limit
	12	4096	TOI Limit
	13	8192	Pmet Limit Fail

Example :STAT:QUES:COND?
>16

Set →

:STATus:QUEStionable:ENABle

→ Query

Description Sets or queries the Questionable Status Event Enable register.

Syntax :STATus:QUEStionable:ENABle <integer>

Query Syntax :STATus:QUEStionable:ENABle?

Return parameter	Bit	Bit Weight	Description
	5	32	Frequency
	8	256	Uncal
	9	512	Limit Fail
	10	1024	ACPLimit
	11	2048	SEM Limit
	12	4096	TOI Limit
	13	8192	Pmet Limit Fail

Example :STAT:QUES:ENAB 4096

:STATus:QUESTionable[:EVENT]?

→ Query

Description Returns the bit weight of the Questionable Status Event register. Reading this register will clear the event register.

Query Syntax :STATus:QUESTionable[:EVENT]?

Return parameter	Bit	Bit Weight	Description
	5	32	Frequency
	8	256	Uncal
	9	512	Limit Fail
	10	1024	ACPLimit
	11	2048	SEM Limit
	12	4096	TOI Limit
	13	8192	Pmet Limit Fail

Example :STAT:QUES?
>16

Set →

:STATus:QUESTionable:NTRansition

→ Query

Description Sets or queries the bit weight of the NTR filter for the Questionable Status register.

Syntax :STATus:QUESTionable:NTRansition <integer>

Query Syntax :STATus:QUESTionable:NTRansition?

Return parameter	Bit	Bit Weight	Description
	5	32	Frequency
	8	256	Uncal
	9	512	Limit Fail
	10	1024	ACPLimit
	11	2048	SEM Limit
	12	4096	TOI Limit
	13	8192	Pmet Limit Fail

Example :STAT:QUES:NTR 32

:STATus:QUEStionable:PTRansition  

Description Sets or queries the bit weight of the PTR filter for the Questionable Status register.


Syntax :STATus:QUEStionable:PTRansition <integer>

Query Syntax :STATus: QUEStionable:PTRansition?

Return parameter	Bit	Bit Weight	Description
	5	32	Frequency
	8	256	Uncal
	9	512	Limit Fail
	10	1024	ACPLimit
	11	2048	SEM Limit
	12	4096	TOI Limit
	13	8192	Pmet Limit Fail

Example :STAT:QUES:PTR 32

:STATus:QUEStionable:FREQuency:
CONDition?



Description Returns the bit weight of the Questionable Status Frequency Condition register.

Query Syntax :STATus:QUEStionable:FREQuency:CONDition?

Return parameter	Bit	Bit Weight	Description
	5	32	Invalid Span/BW

Example :STAT:QUES:FREQ:COND?
>32

:STATus:QUESTionable:FREQuency:ENABLE  


Description Sets or queries the Questionable Status Frequency Event Enable register.

Syntax :STATus:QUESTionable:FREQuency:ENABLE <integer>

Query Syntax :STATus:QUESTionable:FREQuency:ENABLE?

Return parameter	Bit	Bit Weight	Description
	5	32	Invalid Span/BW

Example :STAT:QUES:FREQ:ENAB 32



:STATus:QUESTionable:FREQuency
[:EVENT]? 

Description Returns the bit weight of the Questionable Status Frequency Event register. Reading this register will clear the event register.

Query Syntax :STATus:QUESTionable:FREQuency[:EVENT]?

Return parameter	Bit	Bit Weight	Description
	5	32	Invalid Span/BW

Example :STAT:QUES:FREQ?
>32

:STATus:QUESTionable:FREQuency:
NTRansition  

Description Sets or queries the bit weight of the NTR filter for the Questionable Status Frequency register.


Syntax :STATus:QUESTionable:FREQuency:NTRansition
<integer>

Query Syntax :STATus:QUESTionable:FREQuency:NTRansition?

Return parameter	Bit	Bit Weight	Description
	5	32	Invalid Span/BW

Example :STAT:QUES:FREQ:NTR 32

:STATus:QUESTionable:FREQuency:
PTRansition



Description Sets or queries the bit weight of the PTR filter for the Questionable Status Frequency register.

Syntax :STATus:QUESTionable:FREQuency:PTRansition
<integer>

Query Syntax :STATus:QUESTionable:FREQuency:PTRansition?

Return parameter	Bit	Bit Weight	Description
	5	32	Invalid Span/BW

Example :STAT:QUES:FREQ:PTR 32

:STATus:QUESTionable:ACPLimit:
CONDition?



Description Returns the bit weight of the Questionable Status ACP Limit Condition register.

Query Syntax :STATus:QUESTionable:ACPLimit:CONDition?

Return parameter	Bit	Bit Weight	Description
	0	1	Main channel high fail
	1	2	Main channel low fail
	2	4	Adj1 high fail
	3	8	Adj1 low fail
	4	16	Adj2 high fail
	5	32	Adj2 low fail
	6	64	Adj3 high fail
	7	128	Adj3 low fail

Example :STAT:QUES:ACPL:COND?
>1

Set →

:STATus:QUESTionable:ACPLimit:ENABLE → Query

Description Sets or queries the Questionable Status ACP Limit Event Enable register.

Syntax :STATus:QUESTionable:ACPLimit:ENABLE <integer>

Query Syntax :STATus:QUESTionable:ACPLimit:ENABLE?

Return parameter	Bit	Bit Weight	Description
	0	1	Main channel high fail
	1	2	Main channel low fail
	2	4	Adj1 high fail
	3	8	Adj1 low fail
	4	16	Adj2 high fail
	5	32	Adj2 low fail
	6	64	Adj3 high fail
	7	128	Adj3 low fail

Example :STAT:QUES:ACPL:ENAB 3

:STATus:QUESTionable:ACPLimit[:EVENT]? → Query

Description Returns the bit weight of the Questionable Status ACP Limit Event register. Reading this register will clear the event register.

Query Syntax :STATus:QUESTionable:ACPLimit[:EVENT]?

Return parameter	Bit	Bit Weight	Description
	0	1	Main channel high fail
	1	2	Main channel low fail
	2	4	Adj1 high fail
	3	8	Adj1 low fail
	4	16	Adj2 high fail
	5	32	Adj2 low fail
	6	64	Adj3 high fail
	7	128	Adj3 low fail

Example :STAT:QUES:ACPL?
>3

:STATus:QUEStionable:ACPLimit:
NTRansition

Set →
→ Query

Description Sets or queries the bit weight of the NTR filter for the Questionable Status ACP Limit register.

Syntax :STATus:QUEStionable:ACPLimit:NTRansition
<integer>

Query Syntax :STATus:QUEStionable:ACPLimit:NTRansition?

Return parameter	Bit	Bit Weight	Description
	0	1	Main channel high fail
	1	2	Main channel low fail
	2	4	Adj1 high fail
	3	8	Adj1 low fail
	4	16	Adj2 high fail
	5	32	Adj2 low fail
	6	64	Adj3 high fail
	7	128	Adj3 low fail

Example :STAT:QUES:ACPL:NTR 3

:STATus:QUEStionable:ACPLimit:
PTRansition

Set →
→ Query

Description Sets or queries the bit weight of the PTR filter for the Questionable Status ACP Limit register.

Syntax :STATus:QUESTionable:ACPLimit:PTRansition
<integer>

Query Syntax :STATus:QUESTionable:ACPLimit:PTRansition?

Return parameter	Bit	Bit Weight	Description
	0	1	Main channel high fail
	1	2	Main channel low fail
	2	4	Adj1 high fail
	3	8	Adj1 low fail
	4	16	Adj2 high fail
	5	32	Adj2 low fail
	6	64	Adj3 high fail
	7	128	Adj3 low fail

Example :STAT:QUES:ACPL:PTR 3

:STATus:QUESTionable:SEMLimit
:CONDition?

→ Query

Description Returns the bit weight of the Questionable Status SEM Limit Condition register.

Query Syntax :STATus:QUESTionable:SEMLimit:CONDition?

Return parameter	Bit	Bit Weight	Description
	0	1	Offset 1, Upper fail
	1	2	Offset 1, Lower fail
	2	4	Offset 2, Upper fail
	3	8	Offset 2, Lower fail
	4	16	Offset 3, Upper fail
	5	32	Offset 3, Lower fail
	6	64	Offset 4, Upper fail
	7	128	Offset 4, Lower fail
	8	256	Offset 5, Upper fail
	9	512	Offset 5, Lower fail

Example :STAT:QUES:SEML:COND?
>3

:STATus:QUESTionable:SEMLimit:ENABLE?  

Description	Sets or queries the Questionable Status SEM Limit Enable register.		
Syntax	:STATus:QUESTionable:SEMLimit:ENABLE <integer>		
Query Syntax	:STATus:QUESTionable:SEMLimit:ENABLE?		
Return parameter	Bit	Bit Weight	Description
	0	1	Offset 1, Upper fail
	1	2	Offset 1, Lower fail
	2	4	Offset 2, Upper fail
	3	8	Offset 2, Lower fail
	4	16	Offset 3, Upper fail
	5	32	Offset 3, Lower fail
	6	64	Offset 4, Upper fail
	7	128	Offset 4, Lower fail
	8	256	Offset 5, Upper fail
	9	512	Offset 5, Lower fail
Example	:STAT:QUES:SEML:ENAB 3		


:STATus:QUESTionable:SEMLimit[:EVENT]? 

Description	Returns the bit weight of the Questionable Status SEM Limit Event register. Reading this register will clear the event register.
Query Syntax	:STATus:QUESTionable:SEMLimit[:EVENT]?

Return parameter	Bit	Bit Weight	Description
	0	1	Offset 1, Upper fail
	1	2	Offset 1, Lower fail
	2	4	Offset 2, Upper fail
	3	8	Offset 2, Lower fail
	4	16	Offset 3, Upper fail
	5	32	Offset 3, Lower fail
	6	64	Offset 4, Upper fail
	7	128	Offset 4, Lower fail
	8	256	Offset 5, Upper fail
	9	512	Offset 5, Lower fail

Example :STAT:QUES:SEML?
>3

:STATus:QUESTionable:SEMLimit
:NTRansition



Description Sets or queries the bit weight of the NTR filter for the Questionable Status SEM Limit register.

Syntax :STATus:QUESTionable:SEMLimit:NTRansition
<integer>

Query Syntax :STATus:QUESTionable:SEMLimit:NTRansition?

Return parameter	Bit	Bit Weight	Description
	0	1	Offset 1, Upper fail
	1	2	Offset 1, Lower fail
	2	4	Offset 2, Upper fail
	3	8	Offset 2, Lower fail
	4	16	Offset 3, Upper fail
	5	32	Offset 3, Lower fail
	6	64	Offset 4, Upper fail
	7	128	Offset 4, Lower fail
	8	256	Offset 5, Upper fail
	9	512	Offset 5, Lower fail

Example :STAT:QUES:SEML:NTR 3

:STATus:QUEStionable:SEMLimit:
PTRansition

Set →
→ Query

Description Sets or queries the bit weight of the PTR filter for the Questionable Status SEM Limit register.

Syntax :STATus:QUEStionable:SEMLimit:PTRansition
<integer>

Query Syntax :STATus:QUEStionable:SEMLimit:PTRansition?

Return parameter	Bit	Bit Weight	Description
	0	1	Offset 1, Upper fail
	1	2	Offset 1, Lower fail
	2	4	Offset 2, Upper fail
	3	8	Offset 2, Lower fail
	4	16	Offset 3, Upper fail
	5	32	Offset 3, Lower fail
	6	64	Offset 4, Upper fail
	7	128	Offset 4, Lower fail
	8	256	Offset 5, Upper fail
	9	512	Offset 5, Lower fail

Example :STAT:QUES:SEML:PTR 3

:STATus:QUEStionable:TOILimit:
CONDition?

→ Query

Description Returns the bit weight of the Questionable Status TOI Limit Condition register.

Query Syntax :STATus:QUEStionable:TOILimit:CONDition?

Return parameter	Bit	Bit Weight	Description
	0	1	3 rd lower fail
	1	2	3 rd upper fail

Example :STAT:QUES:TOIL:COND?
>1

:STATus:QUESTionable:TOILimit:ENABLE  

Description	Sets or queries the Questionable Status TOI Limit Event Enable register.		
Syntax	:STATus:QUESTionable:TOILimit:ENABLE <integer>		
Query Syntax	:STATus:QUESTionable:TOILimit:ENABLE?		
Return parameter	Bit	Bit Weight	Description
	0	1	3 rd lower fail
	1	2	3 rd upper fail
Example	:STAT:QUES:TOIL:ENAB 1		

:STATus:QUESTionable:TOILimit[:EVENT]? 

Description	Returns the bit weight of the Questionable Status TOI Limit Event register. Reading this register will clear the event register.		
Query Syntax	:STATus:QUESTionable:TOILimit[:EVENT]?		
Return parameter	Bit	Bit Weight	Description
	0	1	3 rd lower fail
	1	2	3 rd upper fail
Example	:STAT:QUES:TOIL? >1		

:STATus:QUESTionable:TOILimit:NTRansition  

Description	Sets or queries the bit weight of the NTR filter for the Questionable Status TOI Limit register.		
Syntax	:STATus:QUESTionable:TOILimit:NTRansition <integer>		
Query Syntax	:STATus:QUESTionable:TOILimit:NTRansition?		

Return parameter	Bit	Bit Weight	Description
	0	1	3 rd lower fail
	1	2	3 rd upper fail

Example :STAT:QUES:TOIL:NTR 1

:STATus:QUEStionable:TOILimit:PTRansition  

Description Sets or queries the bit weight of the PTR filter for the Questionable Status TOI Limit register.

Syntax :STATus:QUEStionable:TOILimit:PTRansition <integer>

Query Syntax :STATus:QUEStionable:TOILimit:PTRansition?

Return parameter	Bit	Bit Weight	Description
	0	1	3 rd lower fail
	1	2	3 rd upper fail

Example :STAT:QUES:TOIL:PTR 1

:STATus:PRESet 

Description Loads the preset settings.

Syntax :STATus:PRESet

TRACe Commands

:TRACe[:DATA]?	217
:PIXel? TRACe<n>	218

:TRACe[:DATA]? 

Description Returns the trace data for the selected trace in CSV format. There are 601 data points in total.

Query Syntax :TRACe[:DATA]? TRACe<n>


Parameter	<n>	<NR1> 1~4
Return Parameter	<csv data>	Trace data in CSV format: point#1, point#2.....point#n
Example	:TRAC? TRAC1 >5.234e+01,-4.593e+01,-5.533e+01,-4.604e+01,- >5.353e+01,-4.557e+01,-5.280e+0 >1,-4.785e+01,-5.459e+01,-4.578e+01,.....	

:PIXel? TRACe<n>

→ Query

Description Returns the trace *pixel* data (real pixel value x100) for the selected trace in binary coded decimal format, represented by 2 characters per pixel (Highbyte_Lowbyte). Each trace has 601 pixels. In total, the query will return 1203 characters (601x2 + 1 EOF character). If you wish to determine the real value of a pixel simply divide the binary coded decimal character by 100. A binary coded decimal to ASCII lookup table is included in the Appendix on page 227.


The pixel data that is returned is the y-axis pixel data for each nth pixel. The pixel data is taken from the display image data(450 x 600 pixels total).



Query Syntax	:PIXel? TRACe<n>	
Parameter	<n>	<NR1> trace 1~4
Return Parameter	<pixel data>	Pixel data. Returned as ASCII code in binary coded decimal format: pixel1#HbyteLbyte pixel2#HbyteLbyte pixel3#HbyteLbyte.....and so on until the EOF character

Example :PIXEL? TRACE1
>
?H\x16\xA8\x16\xA8\fl\xD4\x1E\x1E\xDCf\xB4F\xB4%
4%\x80%\xE4C\xF8E\$)\x04)hB\xCCC0.\x18-
\xB4D\xC0E\xEC2d2dD\xC0E\xEC5\xE85\.....EOF

For example, data for the first pixel is returned as “?H”, the second as “\x”, the third as “16” and so on. Using the first pixel data as an example, the high byte is “?” and the low byte as “H”. To convert this data into a pixel value, follow the steps below:



TRIGger Commands

:TRIGger[:SEQuence]:DELay 220

:TRIGger[:SEQuence]:DEMod:DELay 220

:TRIGger[:SEQuence]:DEMod:LEVel 221

:TRIGger[:SEQuence]:DEMod:MODE 221

:TRIGger[:SEQuence]:DEMod:SLOPe 221

:TRIGger[:SEQuence]:DEMod:SOURce 222

:TRIGger[:SEQuence]:DEMod:TIME:STARt..... 222

:TRIGger[:SEQuence]:DEMod:TIME:STOP..... 222

:TRIGger[:SEQuence]:EXTErnal:SLOPe 223

:TRIGger[:SEQuence]:MODE 223

:TRIGger[:SEQuence]:PMEtEr:SOURce..... 223

:TRIGger[:SEQuence]:SOURce 224

:TRIGger[:SEQuence]:VIDeo:FREQuency 224

:TRIGger[:SEQuence]:VIDeo:LEVel..... 224

:TRIGger[:SEQuence]:VIDeo:SLOPe..... 225

:TRIGger[:SEQuence]:DELay Set →
→ Query

Description	Sets the trigger delay time in seconds.	
Syntax	:TRIGger[:SEQuence]:DELay <time>	
Query Syntax	:TRIGger[:SEQuence]:DELay?	
Parameter/ Return parameter	<time>	Delay time in seconds
Example	:TRIG:DEL 1.0e-2	

:TRIGger[:SEQuence]:DEMod:DELay Set →
→ Query

Description	Sets the AF trigger delay time in seconds for AM/FM demodulation.	
Syntax	:TRIGger[:SEQuence]:DEMod:DELay <time>	
Query Syntax	:TRIGger[:SEQuence]:DEMod:DELay?	

Parameter/ Return parameter	<time>	Delay time in seconds
--------------------------------	--------	-----------------------

Example :TRIG:DEM:DEL 1.0 ms

:TRIGger[:SEquence]:DEMod:LEVel  

Description Sets the trigger level for AM/FM demodulation.

Syntax :TRIGger[:SEquence]:DEMod:LEVel <NRf>

Query Syntax :TRIGger[:SEquence]:DEMod:LEVel?

Parameter	<NRf>	AM unit = % FM unit = Hz
-----------	-------	-----------------------------

Return parameter	<NR3>
------------------	-------

Example :TRIG:DEM:LEV 10

:TRIGger[:SEquence]:DEMod:MODE  

Description Sets the triggering mode for the AF Trigger in AM/FM demodulation.

Syntax :TRIGger[:SEquence]:DEMod:MODE
{NORMal|SINGle|CONTinuous}

Query Syntax :TRIGger[:SEquence]:DEMod:MODE?

Parameter/ Return parameter	NORMal SINGle CONTinuous	Normal trigger mode Single trigger Continuous trigger
--------------------------------	--------------------------------	---

Example :TRIG:DEM:MODE CONT


:TRIGger[:SEquence]:DEMod:SLOPe  

Description Sets the trigger slope.



Syntax :TRIGger[:SEquence]:DEMod:SLOPe
{POSitive|NEGative}

Query Syntax :TRIGger[:SEquence]:DEMod:SLOPe?



Parameter/	POSitive	Positive slope
Return parameter	NEGative	Negative slope
Example	:TRIG:DEM:SLOP POS	

:TRIGger[:SEQuence]:DEMod:SOURce 

Description	Sets the triggering source for AM/FM demodulation	
Syntax	:TRIGger[:SEQuence]:DEMod:SOURce {IMMEDIATE VIDeo}	
Parameter	IMMEDIATE	Free run trigger
	VIDeo	Trigger on the video signal level
Example	:TRIG:DEM:SOUR IMM	

:TRIGger[:SEQuence]:DEMod:TIME:STARt  



Description	Sets the trigger start time of the AF trigger for the AM/FM demodulation function.	
Syntax	:TRIGger[:SEQuence]:DEMod:TIME:STARt <NRf>	
Query Syntax	:TRIGger[:SEQuence]:DEMod:TIME:STARt?	
Parameter/	<NRf>	Time value in seconds
Return parameter		
Example	:TRIG:DEM:TIME:STAR 2.000e-2	

:TRIGger[:SEQuence]:DEMod:TIME:STOP  

Description	Sets the trigger stop time of the AF trigger for the AM/FM demodulation function.	
Syntax	:TRIGger[:SEQuence]:DEMod:TIME:STOP <NRf>	
Query Syntax	:TRIGger[:SEQuence]:DEMod:TIME:STOP?	

Parameter/ Return parameter	<Nrf>	Time value in seconds
--------------------------------	-------	-----------------------

Example :TRIG:DEM:TIME:STOP 4.000e-2

:TRIGger[:SEQuence]:EXTernal:SLOPe  

Description Sets the external trigger slope

Syntax :TRIGger[:SEQuence]:EXTernal:SLOPe
{POSitive|NEGative}

Query Syntax :TRIGger[:SEQuence]:EXTernal:SLOPe?

Parameter/ Return parameter	POSitive	Positive slope
	NEGative	Negative slope

Example :TRIG:EXT:SLOP POS

:TRIGger[:SEQuence]:MODE  

Description Sets the triggering mode.

Syntax :TRIGger[:SEQuence]:MODE
{NORMAl|SINGle|CONTInuous}

Query Syntax :TRIGger[:SEQuence]:MODE?

Parameter/ Return parameter	NORMAl	Normal trigger mode
	SINGle	Single trigger
	CONTInuous	Continuous trigger

Example :TRIG: MODE CONT

:TRIGger[:SEQuence]:PMETer:SOURce  


Description Sets the triggering source to immediate or external

Syntax :TRIGger[:SEQuence]:PMETer:SOURce
{IMMEdiate|EXTernal}

Query Syntax :TRIGger[:SEQuence]:PMETer:SOURce?


Parameter/	IMMediate	Free run trigger
Return parameter	EXTErnal	External trigger
Example	:TRIG:PMET:SOUR IMM	

:TRIGger[:SEQuence]:SOURce




Description	Sets the triggering source to immediate, external or video.	
Syntax	:TRIGger[:SEQuence]:SOURce {IMMediate EXTErnal VIDeo}	
Query Syntax	:TRIGger[:SEQuence]:SOURce?	
Parameter/	IMMediate	Free run trigger
Return parameter	EXTErnal	External trigger
	VIDeo	Video trigger
Example	:TRIG:SOUR IMM	

:TRIGger[:SEQuence]:VIDeo:FREQuency



Description	Sets the video trigger frequency.	
Syntax	:TRIGger[:SEQuence]:VIDeo:FREQuency <freq>	
Query Syntax	:TRIGger[:SEQuence]:VIDeo:FREQuency?	
Parameter	<freq>	<NRf>
Return parameter	<NR3>	Hz
Example	:TRIG:VID:FREQ? >2.5e+6	

:TRIGger[:SEQuence]:VIDeo:LEVel



Description	Sets the video trigger level.	
Syntax	:TRIGger[:SEQuence]:VIDeo:LEVel <ampl>	
Query Syntax	:TRIGger[:SEQuence]:VIDeo:LEVel?	

Parameter	<ampl>	<NRf> power or voltage.
Return parameter	<NR3>	
Example	:TRIG:VID:LEV 10	

:TRIGger[:SEQuence]:VIDeo:SLOPe

Set →
→ Query

Description	Sets the video trigger slope	
Syntax	:TRIGger[:SEQuence]:VIDeo:SLOPe {POSitive NEGative}	
Query Syntax	:TRIGger[:SEQuence]:VIDeo:SLOPe?	
Parameter/ Return parameter	POSitive	Positive slope
	NEGative	Negative slope
Example	:TRIG:VID:SLOP POS	

UNIT Commands

:UNIT:PMETer:POWer.....	226
:UNIT:POWer	226

:UNIT:PMETer:POWer

Set

Query

Description	Sets the amplitude unit used for the Power Meter mode.	
Syntax	:UNIT:PMETer:POWer {DBM MW}	
Query Syntax	:UNIT:PMETer:POWer?	
Parameter/ Return parameter	DBM MW	Decibels Milliwatts
Example	:UNIT:PMET:POW DBM	

:UNIT:POWer

Set

Query

Description	Sets the amplitude unit used for the Spectrum mode.	
Syntax	:UNIT:POWer {DBM DBMV DBUV W V}	
Query Syntax	:UNIT:POWer?	
Parameter/ Return parameter	DBM DBMV DBUV W V	Decibels decibels relative to one millivolt decibels relative to one microvolt Watt Volt
Example	:UNIT:POW DBM	

A

PPENDIX

ASCII to Binary Coded Decimal Table

Background

The :PIXel query uses binary coded decimal notation when returning the value of each pixel that is displayed. See page 218 for details.

Decimal	Binary	ASCII	Decimal	Binary	ASCII
0	00000000	NUL	64	01000000	@
1	00000001	SOH	65	01000001	A
2	00000010	STX	66	01000010	B
3	00000011	ETX	67	01000011	C
4	00000100	EOT	68	01000100	D
5	00000101	ENQ	69	01000101	E
6	00000110	ACK	70	01000110	F
7	00000111	BEL	71	01000111	G
8	00001000	BS	72	01001000	H
9	00001001	HT	73	01001001	I
10	00001010	LF	74	01001010	J
11	00001011	VT	75	01001011	K
12	00001100	FF	76	01001100	L
13	00001101	CR	77	01001101	M
14	00001110	SO	78	01001110	N
15	00001111	SI	79	01001111	O
16	00010000	DLE	80	01010000	P
17	00010001	DC1	81	01010001	Q
18	00010010	DC2	82	01010010	R
19	00010011	DC3	83	01010011	S
20	00010100	DC4	84	01010100	T
21	00010101	NAK	85	01010101	U
22	00010110	SYN	86	01010110	V
23	00010111	ETB	87	01010111	W

24	00011000	CAN	88	01011000	X
25	00011001	EM	89	01011001	Y
26	00011010	SUB	90	01011010	Z
27	00011011	ESC	91	01011011	[
28	00011100	FS	92	01011100	\
29	00011101	GS	93	01011101]
30	00011110	RS	94	01011110	^
31	00011111	US	95	01011111	_
32	00100000	Space	96	01100000	`
33	00100001	!	97	01100001	a
34	00100010	"	98	01100010	b
35	00100011	#	99	01100011	c
36	00100100	\$	100	01100100	d
37	00100101	%	101	01100101	e
38	00100110	&	102	01100110	f
39	00100111	'	103	01100111	g
40	00101000	(104	01101000	h
41	00101001)	105	01101001	i
42	00101010	*	106	01101010	j
43	00101011	+	107	01101011	k
44	00101100	,	108	01101100	l
45	00101101	-	109	01101101	m
46	00101110	.	110	01101110	n
47	00101111	/	111	01101111	o
48	00110000	0	112	01110000	p
49	00110001	1	113	01110001	q
50	00110010	2	114	01110010	r
51	00110011	3	115	01110011	s
52	00110100	4	116	01110100	t
53	00110101	5	117	01110101	u
54	00110110	6	118	01110110	v
55	00110111	7	119	01110111	w
56	00111000	8	120	01111000	x
57	00111001	9	121	01111001	y
58	00111010	:	122	01111010	z
59	00111011	;	123	01111011	{
60	00111100	<	124	01111100	

61	00111101	=	125	01111101	}
62	00111110	>	126	01111110	~
63	00111111	?	127	01111111	DEL